



## SimaPro Tutorial May 2014





# Colophon

Title:	SimaPro Tutorial
Written by:	PRé Mark Goedkoop, Michiel Oele, Marisa Vieira, Jorrit Leijting, Tommie Ponsioen, Ellen Meijer
Report version: Date: Language: Availability:	5.1 May 2014 English PDF file
Copyright:	© 2002-2014 PRé. Some rights reserved. This work is licensed under the Creative Commons Attribution-Noncommercial-Share Alike 3.0 Netherlands License. To view a copy of this license, visit: http://creativecommons.org/ licenses/by-nc-sa/3.0/nl/deed.en_US or send a letter to Creative Commons, 171 Second Street, Suite 300, San Francisco, California, 94105, USA.
Support:	If the manual is to be used for other purposes, written consent of PRé is needed.
Phone:	+31 33 4504010
Fax:	+31 33 4555024
E-mail:	support@pre-sustainability.com
Website:	www.pre-sustainability.com

# Contents

1.1     THE PURPOSE OF THIS TUTORIAL     5       1.2     THE LESSONS     5       1.3     SIMAPRO TRAINING     6       2     LESSON 1: GENERAL INTRODUCTION; USING THE GUIDED TOUR     7       2.1     THE PROBLEM     7       2.1     THE PROBLEM     7       2.1     THE PROBLEM     7       2.1     USE THE STANDARD USER INTERFACE     8       3     LESSON 2A: ENTERING PRODUCTION PROCESSES     14       3.1     INTRODUCTION     14       3.2     PREPARATION FOR DATA ENTRY     15       3.4     ENTERING PROCESS 1: FELLING THE TREE     16       3.4     PROCESS 2 - SAW MILL (PLANKS')     23       4     LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS     29       4.1     INTRODUCTION     29       4.2     WASTE SCENARIOS     29       4.3     INDEDLING THE INFACTOR FOR LANDRILL     31       4.4     WASTE SCENARIOS     35       5.5     LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE     39       5.3     A PARAMETERIZED SHED     45       6     LESSON 2D: ANALYZING SOME OF THE RESULTS     51       6.1     INVENTORY (LCI) RESULTS     53       6.2     LESSON 2D: ANALYZING SOME OF THE RESULTS     53 <td< th=""><th>1</th><th>INTRODUCTION</th><th>5</th></td<>	1	INTRODUCTION	5
12     THE LESSONS     5       13     SIMAPRO TRAINING     6       2     LESSON 1: GENERAL INTRODUCTION; USING THE GUIDED TOUR     7       2.1     THE PROBLEM     7       2.2     USE THE PREDEFINED WIZARD FIRST     7       2.3     USE THE STANDARD USER INTERFACE     8       3     LESSON 2A: ENTERING PRODUCTION PROCESSES     14       3.1     INTRODUCTION     14       3.2     PREPARATION FOR DATA ENTRY     15       3.3     ENTERING PROCESS 1- FELLING THE TREE     16       3.4     PROCESS 2 - SAW MILL (PLANKS)     23       4     LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS     29       4.1     INTRODUCTION     29       4.2     WASTE TREATMENT RECORD FOR LANDFILL     31       4.3     MODELING THE IMPACTS OF THE OPEN FIRE     34       4.4     WASTE SCENARIOS     35       5     LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE     39       5.1     INTRODUCTION     39       5.2     LESSON 2D: ANALYZING SOME OF THE RESULTS     51       6.1     INVENTORY (LCI) RESULTS     51       6.1     INVENTORY (LCI) RESULTS     51       6.2     LESSON 2D: ANALYZING SOME OF THE RESULTS     51       6.3     CONTRIBUTION ANALYSIS	1.1	THE PURPOSE OF THIS TUTORIAL	5
1.3       SIMAPRO TRAINING       6         2       LESSON 1: GENERAL INTRODUCTION; USING THE GUIDED TOUR       7         2.1       THE PROBLEM       7         2.2       USE THE PROBENED WIZARD FIRST       7         2.3       USE THE STANDARD USER INTERFACE       8         3       LESSON 2A: ENTERING PRODUCTION PROCESSES       14         1.1       INTRODUCTION       14         2.9       PREPARATION FOR DATA ENTRY       15         3.1       ENTERING PROCESS 1: FEILLING THE TREE       16         3.4       PROCESS 2 - SAW MILL (PLANKS)       23         4       LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS       29         4.1       INTRODUCTION       29         4.2       WASTE TREATMENT RECORD FOR LANDEILL       31         4.3       MODELING THE IMPACTS OF THE OPEN FIRE       34         4.4       WASTE SCENARIOS       35         5.5       LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE       39         5.1       INTRODUCTION       39         5.2       LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE       39         5.3       A PARAMETERIZED SHED       45         6.1       LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE       39 <th>1.2</th> <th>THE LESSONS</th> <th>5</th>	1.2	THE LESSONS	5
2       LESSON 1: GENERAL INTRODUCTION; USING THE GUIDED TOUR       7         2.1       THE PROBLEM       7         2.2       USE THE PREDEFINED WIZARD FIRST       7         2.3       USE THE STANDARD USER INTERFACE       8         3       LESSON 2A: ENTERING PRODUCTION PROCESSES       14         3.1       INTRODUCTION       14         3.2       PREPARATION FOR DATA ENTRY       15         3.3       ENTERING PROCESS 1: FELLING THE TREE       16         3.4       PROCESS 2 - SAW MILL (PLANKS)       29         4       LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS       29         4.1       INTRODUCTION       29         4.2       WASTE TREATMENT RECORD FOR LANDFILL       31         4.3       MODELING THE IMPACTS OF THE OPEN FIRE       34         4.4       WASTE SCENARIOS       39         5       LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE       39         5.1       INTRODUCTION       39         5.2       LESSON 2D: ANALYZING SOME OF THE RESULTS       51         6       LESSON 2D: ANALYZING SOME OF THE RESULTS       51         6.1       LESSON 2D: ANALYZING SOME OF THE RESULTS       51         6.1       INVENTORY (LCJN RESULTS <td< td=""><td>1.3</td><td>SIMAPRO I RAINING</td><td>6</td></td<>	1.3	SIMAPRO I RAINING	6
2.1THE PROBLEM72.2USE THE PREDEFINED WIZARD FIRST72.3USE THE STANDARD USER INTERFACE83LESSON 2A: ENTERING PRODUCTION PROCESSES143.1INTRODUCTION143.2PREPARATION FOR DATA ENTRY153.3ENTERING PROCESS 1: FELLING THE TREE164LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS294.1INTRODUCTION294.1INTRODUCTION294.1INTRODUCTION294.2WASTE TREATMENT RECORD FOR LANDFILL314.3MODELING THE IMPACTS OF THE OPEN FIRE344.4WASTE SCENARIOS355LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE395.1INTRODUCTION395.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS516.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS517.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1LESSON 3: BUILDING SOLUTION678.3ANALYZING THE RESULTS519.4ANALYZING THE RESULTS51<	2	LESSON 1: GENERAL INTRODUCTION; USING THE GUIDED TOUR	7
22     USE THE PREDEFINED WIZARD FIRST     7       23     USE THE STANDARD USER INTERFACE     8       3     LESSON 2A: ENTERING PRODUCTION PROCESSES     14       3.1     INTRODUCTION     14       3.2     PREPARATION FOR DATA ENTRY     15       3.3     ENTERING PROCESS 1: FELLING THE TREE     16       3.4     PROCESS 2 - SAW MILL (PLANKS)     23       4     LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS     29       4.1     INTRODUCTION     29       4.2     WASTE TREATMENT RECORD FOR LANDFILL     31       4.3     MODELING THE IMPACTS OF THE OPEN FIRE     34       4.4     WASTE SCENARIOS     35       5     LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE     39       5.1     INTRODUCTION     39       5.2     LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE     39       5.1     INTRODUCTION     39       5.2     LESSON 2D: ANALYZING SOME OF THE RESULTS     51       6.1     LESSON 2D: ANALYZING SOME OF THE RESULTS     51       6.1     INVENTORY (LCI) RESULTS     53       6.3     A PARAMETERIZED SHED     41       7     LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS     61       7.1     THE IMPACT OF THE ALLOCATION PRINCIPLE     61 <td>2.1</td> <td>THE PROBLEM</td> <td>7</td>	2.1	THE PROBLEM	7
23     USE THE STANDARD USER INTERFACE     8       3     LESSON 2A: ENTERING PRODUCTION PROCESSES     14       3.1     INTRODUCTION     14       3.2     PREPARATION FOR DATA ENTRY     15       3.3     ENTERING PROCESS 1: FELLING THE TREE     16       3.4     PROCESS 2 - SAW MILL (PLANKS')     23       4     LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS     29       4.1     INTRODUCTION     29       4.2     WASTE TREATMENT RECORD FOR LANDFILL     31       4.3     MODELING THE IMPACTS OF THE OPEN FIRE     34       4.4     WASTE SCENARIOS     35       5.1     LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE     39       5.1     INTRODUCTION     39       5.2     LESSON 2D: ANALYZING SOME OF THE RESULTS     31       6.1     LESSON 2D: ANALYZING SOME OF THE RESULTS     31       6.1     INVENTORY (LCI) RESULTS     31       6.2     IMPACT ASSESSMENT (LCIA) RESULTS     33       6.3     A PARAMETERS FOR SENSITIVITY ANALYSIS     61       7.1     THE IMPACT OF THE ALLOCATION PRINCIPLE     61       7.2     COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES     63       8     LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD     67       8.1     <	2.2	USE THE PREDEFINED WIZARD FIRST	7
3LESSON 2A: ENTERING PRODUCTION PROCESSES143.1INTRODUCTION143.2PREPARATION FOR DATA ENTRY153.3ENTERING PROCESS 1: FELLING THE TREE163.4PROCESS 2 - SAW MILL (PLANKS)234LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS294.1INTRODUCTION294.2WASTE TREATMENT RECORD FOR LANDFILL314.3MODELING THE IMPACTS OF THE OPEN FIRE344.4WASTE SCENARIOS355LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE395.1INTRODUCTION395.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS516.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.3ANALYZING THE RESULTS70	2.3	USE THE STANDARD USER INTERFACE	
3.1       INTRODUCTION       14         32       PREPARATION FOR DATA ENTRY       15         33       ENTERING PROCESS 1: FELLING THE TREE       16         34       PROCESS 2 – SAW MILL (PLANKS')       23         4       LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS       29         4.1       INTRODUCTION       29         4.2       WASTE TREATMENT RECORD FOR LANDFILL       31         4.3       MODELING THE IMPACTS OF THE OPEN FIRE       34         4.4       WASTE SCENARIOS       39         5.1       INTRODUCTION       39         5.2       LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE       39         5.3       A PRAMETERIZED SHED       45         6       LESSON 2D: ANALYZING SOME OF THE RESULTS       51         6.1       INVENTORY (LCI) RESULTS       53         6.2       IMPACT ASSESSMENT (LCIA) RESULTS       53         6.3       CONTRIBUTION ANALYSIS       61         7       LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS       61         7.1       THE IMPACT OF THE ALLOCATION PRINCIPLE       61         7.2       COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES       63         7.1       THE IMPACT OF THE ALLOCATION PRINCIP	3	LESSON 2A: ENTERING PRODUCTION PROCESSES	14
3.2       PREPARATION FOR DATA ENTRY       15         3.3       ENTERING PROCESS 1: FELLING THE TREE       16         3.4       PROCESS 2 - SAW MILL (PLANKS')       23         4       LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS       29         4.1       INTRODUCTION       29         4.2       WASTE TREATMENT RECORD FOR LANDFILL       31         4.3       MODELING THE IMPACTS OF THE OPEN FIRE       34         4.4       WASTE SCENARIOS       35         5       LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE       39         5.1       INTRODUCTION       39         5.2       THE ASSEMBLY PRODUCT STAGE       39         5.3       A PARAMETERIZED SHED       45         6       LESSON 2D: ANALYZING SOME OF THE RESULTS       51         6.1       INVENTORY (LCI) RESULTS       51         6.1       INVENTORY (LCI) RESULTS       53         6.3       CONTRIBUTION ANALYSIS       56         7       LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS       61         7.1       THE IMPACT OF THE ALLOCATION PRINCIPLE       61         7.2       COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES       63         8       LESSON 3: BUILDING SOPHISTICATE	3.1	INTRODUCTION	14
33ENTERING PROCESS 1: FELLING THE TREE1634PROCESS 2 - SAW MILL (PLANKS)234LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS2941INTRODUCTION2942WASTE TREATMENT RECORD FOR LANDFILL3143MODELING THE IMPACTS OF THE OPEN FIRE3444WASTE SCENARIOS355LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE395.1INTRODUCTION395.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.1INVENTORY (LCI) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	3.2	PREPARATION FOR DATA ENTRY	15
3.4       PROCESS 2 - SAW MILL (PLANKS)       23         4       LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS       29         4.1       INTRODUCTION       29         4.2       WASTE TREATMENT RECORD FOR LANDFILL       31         4.3       MODELING THE IMPACTS OF THE OPEN FIRE       34         4.4       WASTE SCENARIOS       35         5       LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE       39         5.1       INTRODUCTION       39         5.2       THE ASSEMBLY PRODUCT STAGE       39         5.3       A PARAMETERIZED SHED       45         6       LESSON 2D: ANALYZING SOME OF THE RESULTS       51         6.1       INVENTORY (LCI) RESULTS       51         6.2       IMPACT ASSESSMENT (LCIA) RESULTS       53         6.3       CONTRIBUTION ANALYSIS       56         7       LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS       61         7.1       THE IMPACT OF THE ALLOCATION PRINCIPLE       61         7.2       COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES       63         8       LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD       67         8.1       THE PROBLEM       67         8.2       THE SIMAPR	3.3	ENTERING PROCESS 1: FELLING THE TREE	16
4LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS294.1INTRODUCTION294.2WASTE TREATMENT RECORD FOR LANDFILL314.3MODELING THE IMPACTS OF THE OPEN FIRE344.4WASTE SCENARIOS355LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE395.1INTRODUCTION395.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS517LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	3.4	PROCESS 2 – SAW MILL ('PLANKS')	23
4.1INTRODUCTION294.2WASTE TREATMENT RECORD FOR LANDFILL314.3MODELING THE IMPACTS OF THE OPEN FIRE344.4WASTE SCENARIOS355LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE395.1INTRODUCTION395.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.3ANALYZING THE RESULTS67	4	LESSON 2B: ENTERING WASTE TREATMENT AND WASTE SCENARIOS	29
42WASTE TREATMENT RECORD FOR LANDFILL3143MODELING THE IMPACTS OF THE OPEN FIRE344.4WASTE SCENARIOS355LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE395.1INTRODUCTION395.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	4.1	INTRODUCTION	29
4.3MODELING THE IMPACTS OF THE OPEN FIRE344.4WASTE SCENARIOS355LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE395.1INTRODUCTION395.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	4.2	WASTE TREATMENT RECORD FOR LANDFILL	31
4.4WASTE SCENARIOS355LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE395.1INTRODUCTION395.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	4.3	MODELING THE IMPACTS OF THE OPEN FIRE	34
5LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE395.1INTRODUCTION395.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	4.4	WASTE SCENARIOS	35
5.1INTRODUCTION395.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	5	LESSON 2C: ENTERING A COMPLETE PRODUCT LIFE CYCLE	39
5.2THE ASSEMBLY PRODUCT STAGE395.3A PARAMETERIZED SHED456LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	5.1	INTRODUCTION	39
5.3       A PARAMETERIZED SHED       45         6       LESSON 2D: ANALYZING SOME OF THE RESULTS       51         6.1       INVENTORY (LCI) RESULTS       51         6.2       IMPACT ASSESSMENT (LCIA) RESULTS       53         6.3       CONTRIBUTION ANALYSIS       56         7       LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS       61         7.1       THE IMPACT OF THE ALLOCATION PRINCIPLE       61         7.2       COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES       63         8       LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD       67         8.1       THE PROBLEM       67         8.2       THE SIMAPRO SOLUTION       67         8.3       ANALYZING THE RESULTS       70	5.2	THE ASSEMBLY PRODUCT STAGE	39
6LESSON 2D: ANALYZING SOME OF THE RESULTS516.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	5.3	A PARAMETERIZED SHED	45
6.1INVENTORY (LCI) RESULTS516.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS7LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD8.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	6	LESSON 2D: ANALYZING SOME OF THE RESULTS	51
6.2IMPACT ASSESSMENT (LCIA) RESULTS536.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD8.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	6.1	INVENTORY (LCI) RESULTS	51
6.3CONTRIBUTION ANALYSIS567LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	6.2	IMPACT ASSESSMENT (LCIA) RESULTS	53
7LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS617.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD8.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	6.3	CONTRIBUTION ANALYSIS	56
7.1THE IMPACT OF THE ALLOCATION PRINCIPLE617.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	7	LESSON 2E: USING PARAMETERS FOR SENSITIVITY ANALYSIS	61
7.2COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES638LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	7.1	THE IMPACT OF THE ALLOCATION PRINCIPLE	61
8LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD678.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	7.2	COMPARING THE IMPACT OF ALTERNATIVE ALLOCATION PRINCIPLES	63
8.1THE PROBLEM678.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	8	LESSON 3: BUILDING SOPHISTICATED PRODUCT STAGES USING THE WIZARD	67
8.2THE SIMAPRO SOLUTION678.3ANALYZING THE RESULTS70	8.1	THE PROBLEM	67
8.3ANALYZING THE RESULTS70	8.2	THE SIMAPRO SOLUTION	67
	8.3	ANALYZING THE RESULTS	70

# SimaPro (§

9	LESSON 4: USING INPUT OUTPUT DATA	74
9.1	INTRODUCTION	74
9.2	PROBLEM 1: PRIORITIES FOR SUSTAINABLE CONSUMPTION	74
9.3	PROBLEM 2: GUIDING STRATEGIC INVESTMENTS	75
9.4	PROBLEM 3: INCLUDE THE IMPACT OF SERVICES IN THE LCA	75
10	LESSON 5: SOLVING THE WEIGHTING DEBATE	78
10.1	THE PROBLEM	78
10.2	THE SIMAPRO SOLUTION	78
11	LESSON 6: MONTE CARLO ANALYSIS	81
11.1	THE PROBLEM	81
11.2	THE SIMAPRO SOLUTION	81
11.3	RECYCLING OF MODEL PRO	82
11.4	DOES THE RECYCLING SYSTEM SEEM TO BE BENEFICIAL?	84
11.5	MONTE CARLO ANALYSIS	84
11.6	COMPARING UNCERTAINTY PER IMPACT CATEGORY	85
11.7	ABSOLUTE UNCERTAINTY	85
11.8	FINAL REMARK FOR THIS EXAMPLE	87
11.9	UNCERTAINTY ON PARAMETERS	87
12	FURTHER DEVELOPING YOUR SKILLS	89

# 1 Introduction

## 1.1 The purpose of this tutorial

In this tutorial we aim to guide you through your first experience with SimaPro by taking you through a series of simplified examples. The tutorial does not attempt to explain the theory behind LCA and all its methodological issues. The basic theory and main concepts behind LCA are described in the manual 'Introduction to LCA with SimaPro'. This manual can be accessed through the help menu in SimaPro or it can be downloaded from the PRé website http://www.pre-sustainability.com/lca-learning-library. Each lesson in this tutorial starts with a table that summarizes what you should read.

To follow the examples in the tutorial, you need to either have a demo version or a registered version of SimaPro. In terms of software, the demo version is the same as the full version with one important difference: you can enter, edit and save data, but the save command can only be used 16 times. This should be sufficient to do all exercises in this tutorial, but be careful not to waste your limited opportunities to save the data. Please note that reinstalling the demo will not reset the counter.

Please note that this manual has been developed using SimaPro 8.0.3. If you are using another version of SimaPro, your results and screens may differ than what is presented here.

### 1.2 The lessons

We have prepared a number of examples that will allow you to become acquainted with SimaPro. Choosing which examples you would like to follow depends on the amount of time you want to spend and the application you have in mind.

#### Lesson 1: Basic features of SimaPro

We suggest starting with example 1: the guided tour with coffee. The example will show you how a complete LCA is stored and analyzed in SimaPro. It will also explain how you should interpret results, and how the result windows work. It will not explain how you can enter data into SimaPro.

#### Lesson 2 A, B, C, D and E: Entering data and building life cycles

Lesson 2 is a comprehensive example that will take a few hours to complete. It will show you how to build up an LCA: how to enter process data, how to analyze results, and how to perform a simple sensitivity analysis.

#### Lesson 3: Using the wizard to build life cycles

After having done all of the hard work in lesson 2, this lesson will show you how to build a life cycle in a semi-automatic way. In fact, you will build a much more advanced life cycle in a much shorter time. You may, of course, wonder why we made lesson 2 in the first place, but without having experienced making a life cycle "the hard way" you will find it difficult to understand what the wizard does for you and what the results mean.

#### Lesson 4: Using input output data

Input output databases allow you to assess the environmental impact of services and study consumption patterns. They are also useful in screening LCAs or in assessing the importance of missing data. You can find out more about input output databases under Help> SimaPro Manuals.

#### Lesson 5: Addressing the weighting problem

Weighting is a controversial subject in LCA. In many cases you will need to make trade-offs between different impact categories. The weighting triangle is a way to communicate the weighting problem to stakeholders and to come to a decision without using weighting factors.

#### Lesson 6: Assessing uncertainties with Monte Carlo

SimaPro Analyst, Developer and PhD can run Monte Carlo analyses to determine the uncertainty in your results. In the demo you can use the Monte Carlo feature 6 times.



### 1.3 SimaPro training

With this tutorial, you will learn how to use SimaPro by yourself. If you want to develop more advanced skills, PRé and its global partners provide dedicated SimaPro trainings. Please check <a href="http://www.pre-sustainability.com/training">http://www.pre-sustainability.com/training</a> for more information. Some trainings require you to first perform some of the lessons in this tutorial, to ensure that everyone attending the course understands the basics. This also allows for more time to be spent on or more advanced subjects.

2

# 2 Lesson 1: General Introduction; Using the Guided Tour

Overview	
What you will learn	General overview; become familiar with the most important result screens and terminology in SimaPro
Required entry level	Basic understanding of what LCA is about; this is intended to be your first experience with SimaPro
Recommended reading	'Introduction to LCA with SimaPro', chapter 1
Project needed	Introduction to SimaPro
Approximate time needed	20-45 minutes

## 2.1 The problem

Find out what guidelines should be given to designers of coffee machines. For instance, should they focus on material selection or energy efficiency in the use phase? Is the consumption of paper filters important? We will also investigate if it is important to organize a take-back and a recycling system.

### 2.2 Use the predefined wizard first

Open the project Introduction to SimaPro, go to the Wizards section and select the Guided tour (with coffee). The wizard will guide you through some screens and give a generic overview of the capabilities of SimaPro.



In this example, two coffee machines are defined: model Sima and model Pro, with the following specifications:

	Model Sima	Model Pro
Main material for housing	Plastic	Aluminum
System for keeping coffee warm	Hotplate	Thermos jug

These products are analyzed and their environmental impacts are compared.

Take time to go through all 3 chapters in the wizard. This should take around 20 mins.

# SimaPro (S)

### 2.3 Use the standard user interface

After finishing the wizard, you can also go through the example step by step, using the normal interface. This will help you understand the basic features in the interface. This part should take another 20 minutes.

#### 2.3.1 Step 1: Inspect goal and scope

Read the Description of this fictional project under Goal and Scope in the Explorer bar.

Goal and so	ope
	Description
	Libraries

#### 2.3.2 Step 2: Inspect the processes in the database

Click on Processes under Inventory and inspect the range of processes supplied in the database. Choose a process, and double-click it. The process is opened and you can inspect how it is defined.

Inventory
Processes
Product stages
System descriptions
Waste types
Parameters

#### 2.3.3 Step 3: Analyze the environmental profile of a product

Click on Product stages. Expand Assembly and then select Coffee machine (demo). You will see 2 assemblies. These are the basically product definitions.

Double-click Assembly model Sima (plastic); the assembly will be opened and you can see how it is defined.

Wizards	⊡ Product stages	Name 🛆
Wizards	- Assembly	Assembly model Pro (aluminium)
Product Systems	Coffee machine (demo)	Assembly model Sima (plastic)
Develop wizards	···· Sub assemblies (parts)	
Wizard variables	Use phase products	
Goal and scope	Others	
Description	Life cycle	
Libraries	⊡ · Disposal scenario	
Inventory	Disassembly	
Processes		
System descriptions		

Now click the Analyze toolbar button and then Calculate to arrive at the inventory and impact assessment results, as well as the process contributions. The ReCiPe Endpoint H/A method has been selected as the default method. Later in step 10, we will show how you can select another default impact assessment method.

Figure 1 shows the characterization results under the Impact assessment tab. Click the Characterization button if you see a different graph. Since all impact categories have a different unit, they are plotted in a percentage scale. The colors indicate the relative contribution of different parts of the product.

### SimaPro Tutorial



Figure 1: Inventory and impact assessment results

From the many possible uses of the results window we just mention three:

- 1. LCI results: The inventory result is a long list of emissions and resources. Click the Inventory tab. It is on the right side of the Impact Assessment tab.
- 2. With the buttons Characterization, Damage assessment, Normalization and Weighting, you can follow the different impact assessment steps. These buttons are sub tabs of the Impact Assessment tab.
- 3. Process contribution analysis: this shows the relative contribution of each individual process to an impact category or to another indicator.

A special feature of this results window is the possibility to click a graph, or right-click the tables; you will then get the option to further specify the results.

Please feel free to experiment with this important window. Press F1 if you need help or an explanation.



#### 2.3.4 Step 4: Generate a process network

Click the Network tab in the upper left-hand corner of the window. A network flow chart will be generated. A warning message will tell you that the network is not completely visible. This is because by default only twelve processes are shown. SimaPro automatically calculates the influence of a process, then selects a "cut-off value" so that only twelve processes are shown. Please click OK. Now you can see the network of all processes together. Each box represents a process. The arrows present the flows between the processes. The red bars (or thermometers) indicate the environmental load generated by each process and its upstream processes. This is a useful feature, as you can distinguish between important and less important processes (i.e., identify hotspots)

Please note that the colors of the boxes may differ on your screen. You can define your own color settings by right-clicking the background area then selecting Colors.



Figure 2: Process contributions

This window has a wide range of options that you can experiment with. The following are especially interesting:
With the indicator selector single score you can specify which indicator or LCI result is to be represented by the "thermometers" in each process. You can choose any single impact category or inventory result.

• Cut-off setting . Processes that contribute less to a selected indicator than the percentage you have specified here are not shown. In this case the cut-off value is set to 3.5%. When you set it to zero you will also see all processes.

• The split screen 트 button shows the content of the process that is selected in the network.

#### 2.3.5 Step 5: Analyze a full life cycle

Next, you can analyze a full life cycle of the coffee machine. Close or minimize the previous window and click Product stages, expand Life cycle, and then select Coffee machine (demo). You will see 2 product life cycles. Double-click Life cycle model Sima (plastic). Read the comments to see how the functional unit has been defined.

Wizards Wizards Product Systems Develop wizards Wizard variables Goal and scope Description Libraries Inventory	□-Product stages B- Assembly □-Life cycle B- Coffee machine (demo) U- Others B- Disposal scenario B- Disassembly B- Reuse	Name / Life cycle model Sima (plastic) Life cycle Pro, no takeback
Inventory Processes Product stages System descriptions		

Click the **I** button and press Calculate to get an analysis such as the one in step 3, but this time the analysis of the entire life cycle is shown. You can now inspect the relative contribution of the various life cycle stages. Click the Network tab to get the window as seen shown in figure 3.

You can recognize the assembly, the use processes, and the disposal processes. The coffee filter is defined as an additional life cycle, with its own assembly and disposal stage.

# SimaPro (S)



Figure 3: Network

#### 2.3.6 Step 6: Compare two products in the production stage

In addition to model Sima with plastic housing, we also modeled a different coffee machine: model Pro. This one has aluminum housing and uses a thermos jug to keep the coffee warm. Model Sima uses a hotplate.

First, compare the production stages. Select Assembly model Sima (plastic), and while holding down the CTRL key, select Assembly model Pro (aluminium) in the list of assemblies.



Click Compare in and then Calculate. A window will be generated that compares both products by impact category. In this case, interpretation is easy; model Sima has a much lower load than model Pro. If you analyze only model Pro – the way you did with model Sima in step 3 - you will see that this is due to the use of aluminum in the housing.

#### 2.3.7 Step 7: Compare life cycles

Comparing life cycles can be done in the same way. Select Life cycle Sima (plastic) and Life cycle Pro, no takeback. Click Compare in and then Calculate to arrive at a comparison of the environmental impacts of the life cycles of both models. When the life cycles are compared, impact category by impact category in the characterization tab, it appears that the life cycle of model Sima has a higher environmental load for all impact categories.



Click Single score to see a weighted total score for both product life cycles. This clearly shows that model Sima has the higher total environmental load. This is interesting since in the production stage model Sima had the lower environmental load. Apparently the higher energy consumption during the use phase of model Sima determines the outcome.

Note that according to ISO, single scores may not be used for "comparisons disclosed to the public".

#### 2.3.8 Step 8: Perform sensitivity analysis on alternative assumptions

The assumptions regarding the use of the machine are quite uncertain and may even be speculative. There is a special subcategory under the life cycle of the coffee machine that stores life cycles based on other assumptions, for example, regarding intensity of use and life time of the product.



There is also a special version of model Pro where electricity is left out. This allows you to inspect the effect of the take-back system. In lesson 6, this is used in a Monte Carlo uncertainty analysis.

#### 2.3.9 Step 9: Inspect or select a method

In the Impact assessment section in the LCA Explorer, click Methods to view a list of all available impact assessment methods in SimaPro under Methods. In the full version of SimaPro, you can edit these methods and add new ones.



In this section you also can select another default method for your calculations. Click the method name, choose an associated Normalization and Weighting set, and click Set as default.

#### 2.3.10 Step 10: Inspect the interpretation section

The interpretation section is used as a checklist and a framework for your LCA report. The most important interpretation issues according to ISO 14043 can be entered here. The section is filled with an example.

# SimaPro 🗳

# 3 Lesson 2a: Entering Production Processes

Overview	
What you will learn	Get hands-on experience with SimaPro by entering simple data, and building a simple process network that describes the production of planks from a tree
Required entry level	Lesson 1 should be done first
Recommended reading	'Introduction to LCA with SimaPro' chapters 2 and 3 are essential reading material if you wish to understand the background of issues like allocation and system boundary settings
Project needed	Tutorial with wood example
Approximate time needed	45-60 minutes

### 3.1 Introduction

Assume you want to make an LCA of a simple wooden shed to be used in a private garden. The shed is made of just two materials: wood and some steel, for the nails and other metal parts. There is no packaging. We also assume there is no maintenance or paint, there are no windows, no doors and there is no heating or lighting. It is just a simple shed.

There are three basic parts in this modeling exercise:

- 1. Entering processes that describe the environmental impact of cutting a tree and sawing planks at a sawmill. For simplicity, we have ignored the impact of cutting a forest which has an effect on the impact category biodiversity. For the steel used in the shed, we shall use data that is already available.
- 2. Describing the end-of-life of the shed. In doing that, we will demonstrate some of the advanced features in modeling waste scenarios, which are unique to SimaPro. In this example, we will use the assumption that 40% of the wood is burned in open fireplaces at peoples' homes and that 60% goes to a modern landfill.
- 3. Once we have developed the production and the end-of-life scenarios, we will develop the specification of the shed (the assembly) and the life cycle.

While modeling, we will of course encounter some methodological issues. However, these will not be thoroughly analyzed here. Please refer to the 'Introduction to LCA with SimaPro' manual for further information. The data we have used for this LCA is not the best or the most representative and is by no means complete. The purpose here is to learn about SimaPro and not to provide you with accurate data.

### 3.2 Preparation for data entry

If you have a registered version of SimaPro, please read section 3.2.1 and then go to section 3.2.3 after opening the example. If you have a demo version of SimaPro, please start from section 3.2.2.

#### 3.2.1 Starting a registered version of SimaPro

Upon start-up, SimaPro will prompt you to open a project. Select the Tutorial with wood example from the list, and click Open.

#### 3.2.2 Starting from the SimaPro demo version

As long as you have not entered the license code provided by PRé, SimaPro will run in demo mode. In this mode, you can still run this example. SimaPro allows you to save processes 16 times. The example requires you to save 9 processes. From lesson 3 onwards, you will need about 5 saves. You will still have 2 spare "saves" to correct errors or to perform a sensitivity analysis. After 16 saves you will still be able to run the demo and view the results but you cannot make changes.

Reinstalling the demo will not reset the counter.

When you start the demo, it will ask you to register or run in demo mode. Choose the demo mode. Next, SimaPro will ask you which version of SimaPro to use. Choose Analyst. After that, go to the File menu on top of the screen and select Open project, select the Tutorial with wood example project from the list and click Open.

#### 3.2.3 Starting the wood example project

SimaPro organizes all the data you enter into 'projects'. This is useful if you run more than one LCA project, as you can keep data of each project separate. Each project has 4 different sections (see the menu on the left side of your screen) as seen in the LCA explorer:

- 1. Goal and scope: here you describe the purpose of the project.
- 2. Inventory: here you enter and edit your data.
- 3. Impact assessment: here you can edit, enter, select impact assessment methods and save calculation setups.
- 4. Wizards: Here you run the wizards, which are basically guidelines for less experienced users. The step-by-step menu of the LCA Wizard and the Guided tour with coffee are examples of Wizards. In the SimaPro Developer version, you can create your own Wizards.

In the demo, we have predefined all the projects you need; you cannot create your own projects.

#### 3.2.4 Goal and scope

The initial stage in LCA is to go through the Goal and scope definition, namely define all practical details related to the project. It might seem a short and easy step. However, it is highly important, since aspects defined in this step appear in all stages of the LCA and are relevant to the product life cycle. In this example, in order to focus on entering data and building up new processes in SimaPro, we have defined these parameters in advance. Therefore they are already filled in. Please take some time to read the Goal and Scope.

#### Description

In this section, you find information on the goal and the most important choices. The text fields refer to the obligatory issues you need to describe according to ISO 14041. You can cut and paste these texts to your word processor if required. You may use the arrow keys to run through the description menu.

#### Libraries

In this section, you can define which libraries you want to use for this project. Libraries are special types of projects. They are intended to be used as resources that you can use in all your projects and they are not meant to be edited. In case you need to edit an item that is in a library, you can copy the item to your project by selecting the process and pressing the copy button. After that, you can edit and rename the item. This way you keep your libraries untouched for other projects. In this project, we only need the data that is stored in this project and the Methods library.



Keep the library selection as it is. If you select additional libraries, or deselect the Methods library, you will run into difficulties in the next chapter. At a later stage, it might be necessary to select additional libraries. We will explain how you can change libraries later on in this manual.

In the next chapter, we will describe how you enter data in the Inventory section of SimaPro. For now we will focus on the production of planks from wood, needed for the shed. For the steel data we use existing data in the SimaPro database.

### 3.3 Entering process 1: felling the tree

The first process describes the felling of the tree. Before we can enter the data, we will have to collect the data. In this example, we will provide you the following data:

- About 1.25 tons of wood is felled to produce a tree trunk of 1 ton, the rest (branches and tops) is left in the forest. We assume these do not cause emissions, as they are part of the natural processes in the forest. In a full LCA, this assumption should of course be better analyzed.
- We use a chainsaw for felling the trees. The chainsaw data provided in the example is specified as impact per hour. In this example, we use a production rate of 25 tons of wood per hour. This means that for 1.25 tons, we need 3 minutes of chainsaw use.

Now create the process, as follows:

- 1. Click Processes in the LCA Explorer window.
- 2. Click the category Wood.
- 3. Click New; a new and empty process record will appear.



Figure 4: Creating your first new and empty process sheet

#### 3.3.1 Entering process outputs (products)

Figure 5 shows the top section of the process record that appears. At the top you find four tabs, giving access to the four different parts of the process record. Click the tab Input/output.

Follow the four steps shown in the figure below:

- 1. Double-click the white field under the Known outputs to technosphere. Products and co-products; a new line will appear.
- 2. In the Name field, enter the text "Felled tree". Jump to the next field by using the tab key.
- 3. Enter the number 1 under Amount.

4. Double-click the Unit field and choose ton by using the drop-down option. SimaPro can convert units, so it understands that you now have just entered an output of 1 ton of felled trees. It is also possible to use cubic meters, in that case you should first change the quantity from mass to volume.

In the next chapter, we will explain the percentage under Allocation and the Waste type. For now, you can ignore these.



Figure 5: Entering the process output

The next product-input line "Known outputs to technosphere - avoided products" can be ignored, as there are no such products (see also section 4.2, where this option will be used in the landfill process).

#### 3.3.2 Entering inputs

This section describes the inputs to the process (see figure 6 below). Here you enter data about the amount of wood to be extracted from the forest. Note that there are three lines in the record where you can specify inputs:

- 1. Known inputs from nature (resources). Here you can list the resources that are directly taken from natural resources. In this case, the wood that is extracted from the forest. In a process that describes mining, the ore or metal input would be described here. All data you enter here will be included in the inventory result table.
- 2. Known inputs from technosphere (materials and fuels). Here you enter inputs that come from other industrial processes and not from nature.
- 3. Known inputs from technosphere (electricity and heat). This field has the same purpose as in 2.



#### 3.3.3 Input from nature resources

The sequence below is generally used in all fields (except for the output fields).

- 1. Click the grey box (insert line here) under Known inputs from nature (resources) to select it.
- 2. Double-click the blue field. A list of predefined resources is presented.
- 3. Search for wood by scrolling down the list (as it is in alphabetical order), or by typing "wood"- SimaPro will immediately search for the closest match.
- 4. When you find "Wood, unspecified, standing/kg", click Select (or double-click).
- 5. Enter the amount as 1.25 tons (or 1250 kg).

#### 3.3.4 Inputs from technosphere (materials/fuels)

The chainsaw needed to cut the tree has already been predefined in the project. We can enter this as an input from the technosphere (see figure 7). This means that the chainsaw process is linked to the process we are creating. This has the benefit that all emissions and resources needed to operate the chainsaw are in that specific record and we do not have to (re)enter all emissions in the record.



Figure 6: Entering the process inputs



Figure 7: Entering inputs from other processes; in this case the chainsaw

Now we will add the chainsaw by repeating the basic procedure. Double-click the last of the three input fields (electricity and heat). Instead of a list of predefined resources, you get a list of available process outputs. The chainsaw process has been defined in the Processing section under Wood. Note that it is located in the Processing section, not the Material section, which also contains a Wood folder. You can of course also use the Find button to locate this process. This can always be used in case you don't know where to find a certain process.

When you have found the chain sawing process, select it by single clicking it. Then click Select at the top right corner of the window.

The process is specified with time (hours) as a unit. We need to input the average time to fell 1.25 tons of a tree. The wood company estimates that this is on average 3 minutes (0.05 hours). Again, you can use the unit conversion and enter 3 minutes.

#### 3.3.5 Entering emissions and other outputs

The lower part of the window is used to specify emissions and wastes. There are eight different sections:

- 1. Emissions to air
- 2. Emissions to water
- 3. Emissions to soil (usually to express leaching)
- 4. Final waste flows, or wastes in solid form, especially intended to monitor the volume or mass of waste (any leaches and emissions from the wastes should be specified in the other categories)
- 5. Non material emissions, like radiation, noise, etc.
- 6. Social issues
- 7. Economic issues
- 8. Waste and emissions sent to treatment



In the last section you can specify the emissions and wastes that are treated in some form of waste treatment or, for instance, flue gas purification. You can describe precisely how production wastes are handled.

In this example, we will only specify the final waste flow from branches that remain in the forest. The emissions from the chainsaw are already specified in the chainsaw record and should not be specified again as this would result in double counting.

The procedure to specify the waste is the same as in the case of the resources. It is illustrated with the 3 steps in the figure 8. 250 kg of wood is left in the forest as "wood waste".



Figure 8: Entering an environmental impact, in this case a final waste flow

#### 3.3.6 Quick feedback, inspect the tree or network

Now that we have entered the data, we can click the network button **S**, and then Calculate to get a first look at the network we have created. You do not have to save the process at this time; simply click the button while the Felled tree process is being edited. You are now in the Network mode. Click the next tab to switch to Tree mode.



Figure 9: Inspecting the result of your modeling; the felled tree is linked to the chainsaw, and the chainsaw appears to be linked to fuel input

As you can see the top process Felled tree gets an input from the Chain sawing process we have entered. The Chain sawing process has an input for the fuel production and for the production of lubricants. As you can see by entering links between processes, you can build up complete trees. You can also play around using the zooming options and other features. We will not discuss all the features of this window, but nonetheless we will mention a few. The small bars in the processes and line thickness display the contribution to the environmental load. When you click the Show flows in line thickness button indicated in figure 9 you can see the load of a process by the thickness of its line. How this load is calculated depends on the impact assessment method that is currently selected and on which level the method is used. In this figure, the total (weighted) Re-CiPe Endpoint score is used. You can also select alternatives, like using the Climate change impact category indicator result. You can experiment with these settings as much as you want. If you have selected another impact assessment method that does not have a single score, SimaPro will choose one of the impact categories to be displayed. You can return to the process sheet by closing the window with the network.

#### 3.3.7 Documenting a process

Now use the Documentation tab, located beside the Input/output tab of the Felled tree process. If you cannot see this screen, go to Window in the menu and select Previous to go back to the process record. In the Documentation tab, you can specify all types of characteristics of this process record.



Figure 10 provides an example of how such documentation for this specific record could be entered. Please note the following characteristics:

- The name of the process is not the name that you will find in the list with processes. SimaPro uses the outputs as you specified on the Input/output tab as a label. In fact, the name of the process is only there for your own reference.
- Under the image there are fields you can use to characterize the record. In the figure below, the appropriate settings have been entered.
- The comment field in the bottom will also be shown in the listing of the processes in the explorer. It is useful to add some characteristics that help you to understand the contents of the record.

\delta Edit material process 'Felle	ed tree'		
Documentation Input/output	Parameters System description		
Project	Tutorial with wood example	Category	Material
Created on	5-9-2012	Last update on	5-9-2012
Process type	Unit process	Process identifier	employee08445100001
Name	Tree felling		
Status	Finished		
Image			
Time period	1995-1999		
Geography	Europe, Western		
Technology	Average technology		
Representativeness	Average from a specific process		
Multiple output allocation	Not applicable		
Substitution allocation	Not applicable		
Cut-off rules	Less than 5% (environmental relevance)		E
System boundary	Second order (material/energy flows including operations)		
Boundary with nature	Agricultural production is part of natural systems		
Infrastructure process	No		
Date	5-9-2012		
Record	Authors of the tutorial		
Generator	Your name		
General reference and sources Literature reference (Insert line he	s Comment ere)		
Collection method	Taken from literature		
Data treatment	Simplifications made for didactic purposes		
Allocation rules	Not applicable		
Verification	Not done		
Comment	Very much simplified process describing felling of a tree. The assumption according to FSC guidelines. Do not use in other projects.	on is that the correct manageme	nt is sustainable,
	III		

Figure 10: Documentation of the Felled tree process

#### System description

The fourth tab on the top of the process record is called System description. In this example, it is not used and it is not needed. System models are used when a process record does not describe a single "Unit process", but a combination of Unit processes, a so-called "system". For example, the steel processes in the ecoinvent library describe the complete steel production process in a single record, while in fact the steel production process contains many unit processes. By presenting this data, much of the transparency within the processes is lost.

System description provides background information about the way the system model was built. We suggest you inspect some of these system descriptions in the ecoinvent library (or others).

#### Parameters

The third tab is the parameter tab. In chapter 7 we will explain how you can use parameters in your modeling. You do not need this tab right now. Please note that this feature is not available in the Compact, Classroom and Faculty licenses of SimaPro.

Saving data

Click the button with the small diskette symbol in the toolbar to save the data you have entered. You can now close the process record window and go back to the process index. You can see that the Felled tree process is now stored under Wood.

#### Important message for users of the SimaPro demo version:

In this example, you will need to create and store new processes and product stages. After installing a demo version, you can only save 16 changes. After this, the demo can still be used to view results, but there is no way to add or edit data in the databases.

### 3.4 Process 2 - Sawmill ('planks')

Our next objective is to define the sawmill process, where logs are turned into planks, bark and sawdust. In order to do this, we have to create a new process. This is done in the same way as described above. While in the category Materials, Wood, Click New; an empty process record will appear.

This process will convert the felled trees into three products:

- 1. Planks, 50% of the output
- 2. Sawdust, 40% of the output
- 3. Bark, 10% of the output

The remaining wood (250 kg) is used within the sawmill process to dry the wood. This drying process will result in some emissions to air. Furthermore, we will enter the transport needed between the place of felling and the sawmill. As in the case of the chainsaw, we will link to an existing process describing the environmental load of a truck. Finally, we will enter the electricity used in the sawmill, also using a predefined process record describing the electricity production.

#### 3.4.1 Describing the three outputs, waste types and allocation percentages

The fact that the sawmill has three outputs creates an allocation problem. The environmental load of the felling, the transport and the sawmill itself must be allocated over three different outputs: planks, sawdust and bark. In this example, we use mass as an allocation basis. This means that 50% of the environmental load will be allocated to the planks, 40% will be allocated to the sawdust and 10% to the bark.

An alternative solution would be to use the economic revenue of the three products as an allocation basis. The wood generates about 80% of the revenue, with the sawdust generating about 20%, while the bark creates no value. Accordingly, the allocation percentages would be 80% for the planks and 20% for the sawdust.

# SimaPro (S)



Figure 11: The three outputs of the sawmill, and the input of felled trees

Go to the Input/output tab, then:

- 1. Create three lines under Known outputs, by clicking two times on the Insert line here field.
- 2. Type in the names of the three outputs.
- 3. Enter the allocation percentages; in figure 11 above this is done according to mass allocation.
- 4. Click under the Waste type column and select Wood. (The purpose of this step is further explained in the next text box.)
- 5. Click under Known inputs from technosphere (materials/fuels). A selection box will appear where you can select the Felled tree process. If you cannot see it there, use the Find function. To produce 1 ton of products (planks, sawdust and bark) and to have enough wood to burn wood for process energy (250 kg), we need an input of 1.25 tons of felled tree.

Please note that we do not fill in anything under resources. The extraction of wood from the forest is already taken into account in the felling tree process, and should not be repeated (it would result in a double count). In this sawmill process, we put in 1.25 ton of felled tree, while the felling of the tree was defined for one ton. SimaPro will automatically multiply all inputs by 1.25, so you do not need to pay attention to this.

#### The use of waste types

In step 4 you were instructed to set the waste type to wood. A waste type can be seen as a label that is added to a material output. As we will see later, these labels are used in the post-consumption waste scenarios, helping SimaPro recognize which emissions are to be allocated to a material that is incinerated or land filled.

The idea behind this concept is that, in principle, all woods have more or less similar emissions in the waste phase. Similarly, all steels will have similar impacts. By using a standard waste type label, we avoid the task of making specific waste scenarios for every material that is added to the database. As we will explain, you do not have to use the waste types if you consider them too coarse. You can indeed also develop a waste scenario for a specific material.

Waste types do not always have to be specified. Only materials that are specified in the description of the assembly or subassembly need to have a waste type. The felled trees do not need a waste type, as the consumer will not dispose of felled trees but of planks and perhaps sawdust or bark.

Another example is when a consumer disposes of a plastic bag. SimaPro needs to know that this plastic belongs to the waste type plastic, or, more specific, to polyethylene. SimaPro does not have to take into account that this material was oil before it was turned into plastic. The oil that went into the plastic does not need a waste type. If in doubt, always try to specify a waste type, it will never harm.

SimaPro checks with each calculation if materials that are used in assemblies indeed have a waste type.

#### 3.4.2 Adding electricity, transport and emissions

Energy and transport are added in the same way as the Felled tree. We assume a transport distance of 200 km between the forest and the sawmill. For transport we assume that a 16-32 ton lorry is used.



Figure 12: Entering the transport data



The transport process is expressed in ton-kilometers (tkm). One ton-kilometer means the transport of one ton over 1 kilometer, or 1 kg over 1000 km, or any other combination that has the same product of distance and weight. In this case 1.25 tons are transported over 200 km, so you should enter 250 tkm as quantity.

Electricity can be entered in the same way. We assume the processing of the tree occurs in the Netherlands, so we take the Dutch electricity record. You can find this record in the category Energy, under Electricity country mix, Medium Voltage, Market. Different data sources estimate the sawing energy at about 150 kWh per ton output, so you can specify 150 kWh.

As explained, the emissions from transport and electricity are already in the process records you made the links to. However, the emissions for burning of 250 kg wood for drying in the sawmill itself must still be added.

Please enter the following emissions to air:

- 450 kg Carbon dioxide
- 2.9 kg Carbon monoxide
- 500 g Nitrogen dioxide
- 540 g Particulates, <10 µm
- 100 g Sulfur dioxide

The resulting record should look like the figure below (top of the record is not shown)

ocumentation Input/output Parameters System description							
Name		Amount		Unit	Distribution	SD^2 or 2*SD	Min
Felled tree		1,25		ton	Undefined		
(Insert line here)							
Known inputs from technosphere (electricity/heat)							
Name		Amount	Unit	Distribution	SD^2 or 2*SD	Min	Max
Transport, freight, lorry 16-32 metric ton, EURO4 {GLO}  market for   Alloc I	Def, S	250	tkm	Undefined			
Electricity, medium voltage {NL}  market for   Alloc Def, S		150	kWh	Undefined			
(Insert line here)							
	Out	puts					
Emissions to air Name	Sub-compartment	Amount	Unit	Distribution	SD^2 or 2*SD	Min	Max
Carbon dioxide, biogenic		450	kg	Undefined			
Carbon monoxide, biogenic		2,9	kg	Undefined			
Nitrogen dioxide		500	g	Undefined			
Particulates, < 10 um		540	g	Undefined			
Sulfur dioxide		100	g	✓ Undefined			
(Insert line here)			g				
(							
Emissions to water			kg				
Emissions to water Name	Sub-compartment	Amount	kg ton	Distribution	SD^2 or 2*SD	Min	Max
Emissions to water Name (Insert line here)	Sub-compartment	Amount	kg ton kton	Distribution	SD^2 or 2*SD	Min	Max

Figure 13: Entering the emissions from the combustion of some of the wood residues for drying

#### 3.4.3 Inspecting the tree

Like in the previous record, we can now quickly inspect the tree, by clicking the button. The following window will appear, after a message that not all processes are displayed.

SimaPro automatically calculates a cut-off to suppress processes that contribute little to the overall result. Typically, only 12 processes are shown. You can change this in the Options setting in the Tools menu. To determine the relevance, it uses the impact assessment method that you have selected. Processes contributing less than the specified percentage are not shown. If you change the view, for example from Single score to Characterization results of carcinogenics, the cut-off value is applied on the specified results.

Of course, the cut-off only affects the display, not the results. Please feel free to experiment with the cut-off setting.



Figure 14: Inspecting the result of your modeling after entering the chainsaw process

The top process is the Planks process. In fact, SimaPro could have taken one of the other names (sawdust or bark), but as a default for non saved processes it takes the first product you specify. Below the Planks, you see the Felled tree, the transport and the electricity.

Note: depending on the zoom level and the resolution of your monitor, you may not be able to see the full name of the processes. You can adjust the font size by right-clicking on one of the boxes and selecting Font Size.



#### 3.4.4 Documentation

You can complete the record by entering the documentation, as seen in figure 15.

Sedit material process 'Plan	nks'		
Documentation   Input/output	Parameters   System description		
Project	Tutorial with wood example	Category	Material
Created on	5-9-2012	Last update on	7-9-2012
		_	
Process type	Unit process	Process identifier	employee08445100003
Name	Sawmill		
Status	Finished		
Image			
Time period	2000-2004		
Geography	Europe, Western		
Technology	Average technology		
Representativeness	Average from processes with similar outputs		
Multiple output allocation	Physical causality		
Substitution allocation	Not applicable		E
Cut-off rules	Less than 5% (environmental relevance)		
System boundary	Second order (material/energy flows including operations)		
Boundary with nature	Not applicable		
Infrastructure process	No		
Date	5-9-2012		
Record	Authors of the tutorial		
Generator	Your name		
General reference and source Literature reference (Insert line h	es Comment here)		
Collection method	Taken from literature		
Data treatment	Simplifications made for didactic purposes		
Allocation rules	Mass allocation has been used to allocate the environmental load over	r planks, sawdust and bark	
Verification	Not done		
Comment	Production of planks, sawdust and bark from felled trees. Example for	r didactic purposes only; do not u	use in other projects.
•	m		

Figure 15: Entering the documentation of the chainsaw process

Now you can save and close this record. You will note that the number of processes under Wood has now become 4, as all three outputs appear as separate materials, while in fact they refer to the same process.

# 4 Lesson 2b: Entering Waste Treatment and Waste Scenarios

Overview	
What you will learn	How to develop a waste scenario and the associated waste treatments. Often SimaPro users select one of the predefined waste scenarios without really knowing how these work. In this lesson you get a much better understanding of these features.
Required entry level	Lesson 2a should be completed first
Recommended reading	'Introduction to LCA with SimaPro'. Section 8.5 gives a background on how waste and disposal scenarios are developed. It is recommended, but not essential, to read this section first.
Project needed	Tutorial with wood example
Approximate time needed	60-90 minutes.

### 4.1 Introduction

In lesson 2a you created the model for the production of wooden planks. We will now examine the end-of-life stage and start to develop a waste scenario. For many commonly used materials, SimaPro provides standard data. For this tutorial it is useful to develop your own simplified scenario for post-consumption waste. Although we have not defined the shed itself, it will only contain two materials:

- 1. The planks we have defined in the previous chapter.
- 2. Steel parts like nails, screws and other metal construction parts.

This means that the waste model should at least contain data on the end-of-life stages of wood and steel.

This tutorial does not aim to be sophisticated, yet complex enough to show the main features. The characteristics of the scenario are as follows:

- 40% of the wood is burned in open fires at people's homes. In this case, we assume a zero contribution to room heating. As such, open fires are inefficient and in fact cause large energy losses due to the uncontrolled ventilation through the chimneys. Of course, in a real LCA this issue deserves further attention.
- 60% of the wood is dumped in a modern landfill. Again for simplicity, we assume that this landfill has a collection system for methane and that 31% of the emitted methane is used as fuel.

#### Describing the waste scenarios

When we analyze this scenario, we will see that we need to split the waste in different routes. The first split is between 40% burning in open fires, and 60% landfills.

A second split is between the wood and the nails. Although we cannot assume that the consumer will indeed take out the nail, for our modeling purpose it is useful, as steel behaves differently than wood when it is burned. As we explained above, we will use the so-called waste types to make this split. In landfill a similar split should be made, but for now we will ignore this.

SimaPro has a powerful tool to model such splits, the waste scenario. The waste scenario can be used as a generic splitter, and a waste type specific splitter (wood and nails). However, before we model these, we should also discuss how we model the emissions from the waste.

# SimaPro (S)

#### Describing the impacts of waste treatments

Waste scenarios only describe where the waste flows go, and not the emissions that come from the waste treatment. To describe these, SimaPro has another type of process under the Inventory> Processes section: Waste treatment. A waste treatment record contains data on the emissions from, for instance, a waste incinerator or a landfill.

For this example we need the waste treatments:

- 1. A waste treatment that describes the emissions from the open fire when the wood is burned
- 2. A waste treatment that describes the emissions from the open fire when steel nails are burned (if any)
- 3. A waste treatment that describes the emissions from the landfill

#### The positive impacts of some waste treatments

Wood in a landfill will slowly decompose and form methane and carbon dioxide in the first 150 years. About 20% will not decompose and will remain in the landfill as a stable material. The methane part can form a potentially high impact on global warming, as the release of 1 kg contributes over 20 times as much to climate change as the release of 1 kg carbon dioxide. For this reason landfills are being equipped with a methane collection system.

In this example, we assume that most of the methane that is formed in the landfill is collected and used as fuel, or simply burned, as it is better to have an emission of carbon dioxide than methane. By using the methane as fuel, we may assume less natural gas needs to be produced.

To model the useful application of waste or by-products, SimaPro has an "avoided products" option. If you enter a certain amount of natural gas here, SimaPro will subtract the emissions and resource use associated with the production of natural gas. In ISO terms, this principle is referred to as expansion of system boundaries (see chapter 2 of the 'Introduction to LCA with SimaPro' manual for a more elaborate explanation).

### 4.2 Waste treatment record for Landfill

Waste treatment records can be found at the bottom of the Inventory> Processes section. The way to create them and enter the data is quite similar to creating Material processes.

Please enter the data as presented in figure 16, in which a step-by-step procedure is given.



Figure 16: Entering the input to a waste treatment process, and specifying for which waste type this process is valid

- 1. Go to Waste treatment, Transformation under Processes, select the Landfill category. Click New on the right hand side to create a new waste process.
- 2. Enter the name of the waste treatment 'Landfill of wooden shed'. Please note that this is the name referring to the input and not to the output of the process. In a waste treatment the input determines the use of the process. Enter 1 kg as the amount.
- 3. Now double-click under Default material/waste type, to get another selection box. Here you define for which waste types this process is valid. Select Wood from the list of already defined waste types. You will note that "our processes" plank, sawdust and bark will appear in the right-hand window, indicating that these processes are defined with the waste type Wood. Click Waste type to select the waste type wood. As the name of this field suggests, you can also choose to make this waste type only valid for one particular material using the Select button. For example to select Planks only instead of waste type Wood. You can do this later.

# SimaPro \delta



Figure 17: Entering data on the avoided products

- Step 4: Click under Known outputs to technosphere, avoided products. A selection box will appear.
- Step 5: We assume that the use of methane means less natural gas needs to be produced elsewhere. Thus, select Natural gas, from high pressure network (1-5 bar), at service station {GLO} | market for | Alloc Def, S from Materials/Fuels/Natural Gas/Market. We also assume that 0.007 kg methane is used for energy production.

	Step 6: Enter transport between the municipal waste collection point and landfill (20 km)	Step 7: En methane le the total C	ter remai eakages a O <sub>2</sub> emiss	ning and ions		
		Ind	luts			
Known inputs from nature (res Name	ources)	Sub-compartment	Amount	Unit	Distribution	SD^2 or 2*
	(Insert line here)					
Known inputs from technosphe Name	ere (materials/fuels)	$\setminus$ /	Amount		Unit	Distribution
Transport, freight, lorry 16-32	2 metric ton, EURO4 {GLO}  market for   Alloc De	f, s	0,02		tkm	Undefined
	(Insert line here)	/				
Known inputs from technosphe Name	ere (electricity/heat)		Amount	Unit	Distribution	SD^2 or 2*
	(Insert line here)					
		Out	puts			
Emissions to air						
Name		Sub-compartment	Amount	Unit	Distribution	SD^2 or 2*
Methane, biogenic		·	0,002	kg	Undefined	
Carbon dioxide, biogenic	(Insert line here)		0,5	кg	Undefined	
	(unservinite field)					
Emissions to water						

Figure 18: Entering transport and some emissions

- Step 6: Enter under Known inputs from technosphere (materials/fuels) the transport for the distance between the municipal waste collection center and the landfill Transport, freight, lorry 16-32 metric ton, EURO 4 {GLO}| market for | Alloc Def, S. To transport 1 kg over 20 kilometers we need a transport amount of 0.001 ton x 20 km = 0.02 tkm.
- Step 7: Under Emissions to air, enter the emission of the methane that is not collected (0.002 kg) and the total carbon dioxide emissions (0.5 kg).

You could also specify some remaining waste under final waste flows. We assume that all wood is decomposed, so there will be no remaining waste in the long term. Some LCA practitioners also register the 1 kg of landfilled waste to quantify the amount of waste. This way they can report on the short-term waste problem. The choice is yours.

You can now document the record, using the documentation tab, (as previously described) and save it. There is now one new topic: Waste treatment allocation. Here you can specify that we do indeed use full substitution (see figure 19). You can close the process and check the tree or network again.

# SimaPro (S

Time period	2000-2004
Geography	Europe, Western
Technology	Average technology
Representativeness	Average from processes with similar outputs
Waste treatment allocation	Full substitution by distant proxy (different process)
Cut-off rules	Not applicable
System boundary	Second order (material/energy flows including operations)
Boundary with nature	Not applicable

Figure 19: The documentation for this waste treatment record

### 4.3 Modeling the impacts of the open fire

In case of the open fire, the waste treatment is a bit easier to enter. We assume no useful by-products that result in avoided emissions. If a well-designed wood stove would replace the open fireplace, for example, we should then model the savings on the central heating as an avoided product.

Go to Waste treatment/Transformation/Incineration and create a new waste treatment record. Please fill in the record for the open fire as in the example below (figure 20). The airborne emissions come from the Dutch emission registry (not all emissions are entered).

Name	Default material / waste typ	oe Amou	nt Unit		Quantity	Categor	у
Open fire fuelled by material from shed	Wood	1	kg		Mass	Incinera	ition
Known outputs to technosphere. Avoided products Name		An	nount	Unit		Distribution	SD/
(Insert line here)							
		Inputs					
Known inputs from nature (resources)							
Name	Sub-compartme	nt An	nount	Unit	Distributio		n SD4
(Insert line here)							
Known inputs from technosphere (materials/fuels) Name	Amount			Unit	Distributior	sD^2∍Min	Max Comm
(Insert line here)							
Known inputs from technosphere (electricity/heat) Name		An	nount	Unit		Distribution	SD/
(Insert line here)							
		Outputs					
Emissions to air							
Name	Sub-compartme	nt An	nount	Unit	Dist	ribution	SD^2 or
Carbon dioxide, biogenic		1,	2	kg	Und	defined	
Carbon monoxide, biogenic		50	)	g	Und	defined	
NMVOC, non-methane volatile organic compounds, unspecified origi	n	27	7,5	g	Und	defined	
PAH, polycyclic aromatic hydrocarbons		40	)	mg	Und	defined	
Particulates, < 10 um		2,	5	mg	Und	defined	
Nitrogen dioxide		2		g	👻 Und	defined	
(Insert line here)				,			

Figure 20: Entering the data for the open fireplace

You can now also document this record, as we have done in the earlier processes. When you press the X to close this window or press the escape key, SimaPro will ask you if you want to save this process; please do so.

### 4.4 Waste scenarios

Now that we have created the waste treatments, we continue and create the waste scenarios. These describe how much of the waste goes to which treatment. We need three scenarios:

- 1. One for landfill
- 2. One for the open fire
- 3. One that splits up the waste between open fire and landfill

#### 4.4.1 Waste scenario for landfill

In real life, the materials sent to landfill are not split. However for modeling purposes it is useful to use a waste scenario as a 'splitter'. This ensures wood is sent to the waste treatment for wood, while nails and other metal parts are sent to an already predefined waste treatment for steel. These waste treatments each describe specific emissions for the treatment of a specific material.

Under Processes, go to Waste scenarios and choose subcategory Landfill. Click New to get an empty waste scenario record. Now we can fill in the data:

Step 1: enter the name of this scenario and the amount

Step 2: click under Materials and/or waste types separated from waste stream

Step 3: select the landfill waste treatment we just created

Step 4: select the waste type Wood and enter 100%

The data we just entered will be interpreted as follows: all materials with waste type Wood coming into this waste scenario are sent to the waste treatment record Landfill of wooden shed.



Figure 21: Entering the name and one of the outputs of a waste scenario

# SimaPro (§

In the same way, we can now enter the destination of the metal parts. The following figure shows how you can enter the rest of the data.

Step 5: Add a link to Scrap steel (waste treatment) {CH}  treatment of scrap steel, inert material landfill, Alloc Def, S; you can find this under Waste treatment/ Transformation/Landfill/Inert material landfill			Step 6: S type and	6: Specify waste and add 100%			Step 7: Add a link to Unspecified; you can find this under Waste treatment/Others		
				$\land$					
Documentation Input/output Parameters	System description								
			Products		+		_/_		
			Troducto		+		/		
Waste specification		11-3			<b>_</b>	/			
Name	Amount	Unit Ca	tegory ndfill		Comment				
	-			1		/			
			Inputs						
Variani izante fran tarkarankara (matariala (fr				1					
Nown inputs from technosphere (materials/full	es)		Am	unt	X	Ur	nit	Distribution	SD^2
(In	nsert line here)								
Known inputs from technosphere (electricity/he	eat)		/						
Name	11 I. N		Arh	ount	Unit	D	istribution	SD^2 or 2*SD	Min
(11	isert line here)		X		$\longrightarrow$				
			Outputs						
Materials and/or waste types separated from v	waste stream								
Waste scenario/treatment			Material / Waste	type	Percentage	Commer	nt		_
Landfill of wooden shed			Wood		100 %				
Scrap steel (waste treatment) {CH}  treatmen	nt of scrap steel, inert ma	aterial landfill   Alloc D	Steel		100 %				
(Insert lin	he here)								
Waste streams remaining after separation			Perc	entere		Comment			
Unspecified			100	%		All mater	ials that do no	t belong to one of	
(In	sert line here)		_			the wast Please b have any should n	e types go to eware, this tro y emissions, so ot see it in the	Unspecified. eatment does not o normally you tree or network.	
(and concerned)									
•	III								P.

Figure 22: Entering the other outputs of the waste scenario
You can now enter the documentation of the process, as described earlier.

#### What has been realized now?

All materials with waste type Wood that enter this record are sent to the waste treatment Landfill of wooden shed. All metals with waste types steel are sent to the landfill of steel waste treatment. All other materials are sent to the waste treatment Unspecified.

#### 4.4.2 Waste scenario for the open fire

Go to Waste scenario, select category Incineration and create a record as below. For the steel, we use predefined records. Of course, these waste treatments are not representative of an open fire. However, as the amount of steel is low this is acceptable. You can now enter the documentation of the process.

	· · ·									
			Pr	oducts						
Waste specification										
Name	Amount	Unit	Category		Com	ment				
Open fire waste scenario for shed	1	kg	Incineratio	n						
			I	nputs						
Known inputs from technosohere (materials/fuels)										
Name				Amount			Unit		Distribution	SD^2
(Insert	line here)									
Known inputs from technosphere (electricity/heat)										
Name				Amount	Ur	nit	Distr	ibution	SD^2 or 2*SD	Min
(Insert	line here)									
			0	utputs						
Materials and/or waste types separated from wast Waste scepario/treatment	e stream			Material / Waste t	vne	Percentan	e Co	mment		
Open fire fuelled by material from shed				Wood	ype	100 %		minerie		
Scrap steel (waste treatment) {CH} treatment of	scrap steel, munic	inal incineratio	n LAlloc Def. S	Steel		100 %				
(Insert lin	ne here)	apar internet area	in prince being b	Bucch		100 /0				
Waste streams remaining after separation	,									
Waste scenario/treatment				Percentage		Co	mment			
Unspecified				100 %						
(Insert	line here)									
<										•

Figure 23: The waste scenario for the open fire

#### 4.4.3 Waste scenario for splitting waste stream

Finally, we develop a waste scenario that splits the waste stream into two:

- 1. 40% is used in open fires
- 2. 60% is sent to the landfill

This waste scenario can be made in the category Others. It is relatively easy to make. Just follow the steps in figure 24.



Figure 24: Entering the waste scenario that splits the waste over landfill and open fireplaces

In step 2 we added the transport between the user and the municipal waste collection point. The mass specified in the top line refers to the inputs of the waste flow, in this case the shed.

Please note that in step 3 of this scenario, we do not specify any waste types. We just added percentages to specify how the waste is divided over the different treatments.

You can now enter the documentation of the process. Upon closing the record, SimaPro will warn you that nothing has been specified for the remaining waste. In this case, you can ignore this, as all waste types are sent to their specific waste scenarios which in themselves will take care of any remaining waste.

You cannot have an overview of the waste scenario with a tree. SimaPro doesn't yet know which materials will be in the waste stream. We first have to define the life cycle and input to the waste stream. After defining the life cycle, we can see the structure.

## 5 Lesson 2c: Entering a Complete Product Life Cycle

Overview	
What you will learn	Using the process planks developed during lesson 2a and the waste scenario in lesson 2b, we will now develop a complete life cycle of a simple wooden shed. Now you will not work with processes, but with product stages, like assemblies and life cycles.
Required entry level	Lesson 2a and 2b should be completed first, although it is possible to skip 2b. Instead you can use a standard waste scenario. In that case, the results will differ from what you will see in this tutorial.
Recommended reading	'Introduction to LCA with SimaPro'. Chapter 8 provides some background. It is recommended, but not essential to read it. For the parameter example we recommend reading chapter 10
Project needed	Tutorial with wood example
Approximate time needed	45-60 minutes

### 5.1 Introduction

Now we have seen how process trees are built up in SimaPro. We created a process that describes the impacts of making planks and prepared waste treatments and scenarios.

The next step is to describe the product and its life cycle. SimaPro uses a different type of record to describe products and life cycles: Product stages. Product stages do not contain environmental information but refer to processes like the ones we defined in chapter 3. In this tutorial we will use 2 out of 5 available product stages:

 $\cdot$  The assembly is used to describe the shed

• The life cycle is used to describe the use phase of the shed and links to the waste scenario

The three other product stages are not explained here. They are useful if you want to define relatively complex disassembly and reuse scenarios.

### 5.2 The assembly product stage

This models the assembly of the shed in a simplified way. The following steps show you how to enter the following data:

- The shed is made of 150 kg planks. There are no sawing losses, no packaging.
- About 2 kg of steel parts are used, representing screws, nails etc.
- The consumer picks up the wood with his or her private car, and drives on average, 5 km to and 5 km from the shop. We disregard the possibility that other things are purchased on the same trip, which would require some form of allocation.

Figures 25 through 27 explain all 11 steps required to create the assembly.



Figure 25: Creating an assembly and entering its name

In figure 26, we will link the assembly to the plank process. Please note that in step 5, where you click the field under Materials/Assemblies, you can choose between entering materials and subassemblies. This shows that you can also create subassemblies, which is useful for more complex designs. For instance, we could create a separate subassembly for a window, door, or floor, each with different specifications.

### SimaPro Tutorial



Figure 26: Entering the link to the planks

## SimaPro (§



Figure 27: Finalizing the assembly

After step 11, you can save and close the assembly.

#### 5.2.1 Inspecting the network

To get an overview of what you have just been modeling, we suggest you click the subtract to show the network. SimaPro will give you a warning that not all processes are shown. It calculates a cut-off level in such a way that only the 12 most important processes are displayed. The processes that contribute less than that level are not shown (although their contribution counts in the result of course). You can still see the process Planks, but felling of the tree and the chainsaw are not visible. If you adjust the cut-off, you can make these visible too.

In figure 28, the thickness of the line represents the environmental load of the flow according to the ReCiPe Endpoint score. You can switch this function on or off, using the indicated button.

### SimaPro Tutorial



Figure 28: Inspecting the result of your modeling. Note that not all processes are shown

#### 5.2.2 The product life cycle

The product life cycle is created in the same way as an assembly. Only three steps are needed:

- 1. Under Product stages, Life cycles, Others, create a new life cycle and add a name to it.
- 2. Create a link to the assembly. A life cycle can only contain one assembly.
- 3. Create a link to the waste scenario. A life cycle can only contain one waste scenario or one disposal scenario.

## SimaPro 🗳



Figure 29: Life cycle of the shed. Here the assembly is linked to the end-of-life phase

#### 5.2.3 Inspecting the process structure

Now we can get a complete overview of the life cycle, and we can see the end-of-life scenario, by clicking the Tree or Network button. Again not all processes are shown, but we can clearly see the assembly (blue), the life cycle (yellow), and the waste scenario.



Figure 30: Inspecting the results of your modeling; the life cycle overview

### 5.3 A parameterized shed

Instead of using fixed values for the dimensions of the shed, you can make use of parameters in SimaPro. In this section we will demonstrate how this is done, and how you can use this feature to quickly analyze the impact of changing values.

Please note that this feature is not available in the Compact, Classroom and Faculty licenses of SimaPro.

In the assembly Simple shed defined in section 5.2, we simply added the total mass of wood needed. Of course the total amount of wood depends on the dimensions of the shed. The table below lists the dimensions that the shed consists of.

Dimension	Value	Unit (remark)
width	3	meter
length	2	meter
height	2	meter
roof_slope	0.5	slope expressed in radials (57.3 degrees = 1)
roof_overhang	0.2	meter (the roof is larger than the walls)
wall_thickness	0.0022	meter
sp_mass_wood	800	kg/m <sup>3</sup>
roof_thickness	0.003	meter

With these parameters, SimaPro can do a number of calculations. For example the wall surface can be calculated as twice the front and back wall (2\*height\*width) plus the two side walls (2\*height\*length).

If the roof is sloped, we can also add the triangular parts just under the roof. The size depends on the roof angle, thus you need to calculate the tan (roof angle) to get the surface of that area. The angle also determines the roof area, and for this you need to know the cosine of the roof angle.

The table below gives an idea of the calculations SimaPro can do for you: it calculates the surface of the roof and the walls, and it can calculate the volume and mass of the wood needed to build the shed.

Dimension	Value	Unit (remark)
roof_surface	2*(length + 2*roof_overhang) * (2*roof_overhang + width/cos(roof_slope))	the size depends on overhang, roof slope, length and width
wall_surface	2*width*height + 2*length*height + 2*width*tan(roof_slope)*width	the last part refers to the triangular part of front and back, under the roof
wood_volume	wall_thickness*wall_surface + roof_thickness*roof_surface	m³
wood_mass	wood_volume*sp_mass_wood	kg

To enter this data and the formulas, please open assembly Simple Shed, and go to the Parameters tab. Here you can enter the data and formulas as shown in figure 31.

			Equal si added b	gn and ı y SimaF	result Pro	: are	
Input/output Parameters							
Name	Value	Distribution	SD^2 or 2*SDMin	Ма	x	Hide	Comment
width	3	Undefined		1			meter
length	2	Undefined					meter
height	2	Undefined					meter
roof_slope	0.5	Undefined					slope expressed in radials (57.3 degrees = 1)
roof_overhang	0.2	Undefined					meter
wall_thickness	0.0022	Undefined					meter
sp_mass_wood	800	Undefined					kg/m3
roof_thickness	0.003	Undefined					meter
(Insert line here) Calculated parameters Name	Expression						Comment
roof_surface	2*(length+2	*roof_overhang)	*(2*roof_overhang-	+width/cos(ro	of_slope	)) = 18.3	the size depends on overhang, roof slope, length and width
wall_surface	2*width*heig	ht+2*length*he	ight+2*width*tan(ro	oof_slope)*wi	idth = 29	.8	the last part refers to the triangular part of front and back, under t
wood_volume	wall_thicknes	s*wall_surface+	roof_thickness*roof	_surface = 0.	121		m3
wood_mass	wood_volum	e*sp_mass_wood	= 96.5				kg
(Insert line here)							
•							•
No Error		Additional inf	ō				

Figure 31: Parameters that describe the size of the shed, and a number of formulas that determine surface, volume and mass

Should you make a typing error, a message will be displayed at the bottom of the window. In the section Calculated parameters, you do not need to add the equal sign and the calculated result. SimaPro will do this for you when you press Enter.

Next, you can go to the Input/output tab of the assembly and update the data, as shown in figure 32. In this example, we also added a steel plate roof. The surface of the roof is also parameterized, and will change with changes you make in the dimensions. In a similar way, a layer of paint can be added to the assembly using the wall surface parameter.

### SimaPro 🗳

For clarity, the screws and other metal parts and the roof are modeled separately. However, the two could be combined into one material.



Figure 32: A more sophisticated assembly of a shed. The amounts of material are calculated using parameters. A roof is added.

- Once these parameters are defined, you can easily determine:
- 1. the total amount of wood that will go into the shed
- 2. the amount of roofing material needed

The advantage of using the parameter feature is that by changing the value of just one or more parameter, you can analyze different versions of the same product and find an optimal solution. In chapter 7, we will show you how to make comparisons for alternative shed designs using parameters.

#### Further sophistication

In general, planks come in standard width and length size. If you design a wall with a length of 2 meter while a standard length is 2.10, you lose 10 centimeters, or 5% of each plank. If you design a 1.90 meter wall you lose even more.

In SimaPro you can calculate how much you lose by taking the "modulo" of the designed wall length and the nearest standard length. The modulo is the remainder after a division. For example, we have a plank of 70 cm and we need pieces of 20 cm. We saw 3 pieces of 20 cm and have a remainder of 10 cm, the modulo is 10 cm. You can also do this for the roof panels and the width of the planks. You can use this to model waste treatment of sawing losses.

**5.3.1 Operations and expressions** The table below gives an overview of the operations you can perform with parameters:

Symbol	Explanation
+	Add
-	Subtract
*	Multiply
/	Divide
^	Power
Div	Divide Int, returns only the integer part of a division
Mod	Modulo (what remains after a division)
>	Greater than
<	Smaller than
=	Equal
<>	Unequal
>=	Greater than or equal to
<=	Smaller than or equal to
And	Logical And
Or	Logical Or
Xor	Logical Xor
NOT	Logical Not

## SimaPro (§

You can also use the following mathematical and logic functions:

Symbol	Explanation
SQR	Square value for x (= x^2)
SQRT	Square root value for x
ABS	Absolute value of x
TRUNC	Integer part of x (same as Int(x))
INT	Integer part of x
FRAC	Fractional part value of x
ROUND	Rounds x to the nearest integer value
CEIL	Ceil integer value of x
FLOOR	Floor integer value of x
IFF	If L<>0 then A else B
MAX	Maximum value of input values x1 x2 x3
MIN	Minimum value of input values x1 x2 x3
EXP	Exponent value for the x
LN	Natural logarithm value of x
LG	Decimal logarithm value of x
POWER	x to a power of y (y is floating point value)
IPOWER	x to a power of y (y is integer value)
SIN	Sine value of x
COS	Cosine value of x
TAN	Tangent value of x
COTAN	Cotangent value of x
ASIN	Arcsine value of x
ACOS	Arccosine value of x
ATAN	Arctangent value of x
SINH	Hyperbolic sine value of x
COSH	Hyperbolic cosine value of x
TANH	Hyperbolic tangent value of x
NOT	Logical NOT of x (if x=0; 1 else 0)

6

# 6 Lesson 2d: Analyzing some of the Results

Overview	
What you will learn	How to generate results and interpret them; how to perform contribution analysis per process or per group of processes
Required entry level	Lesson 2a, 2b and 2c should be completed first, If you have skipped 2b and used a standard waste scenario the results will be different from the results in this tutorial.
Recommended reading	'Introduction to LCA with SimaPro', chapters 4 and 5
Project needed	Tutorial with wood example
Approximate time needed	45-60 minutes

### 6.1 Inventory (LCI) results

So far, we have analyzed the tree as an intermediate check of our work. Now we will discuss a few of the other results. We will only show a few of the many possibilities available in SimaPro, and we suggest that you experiment with other functionalities yourself. If in doubt about the meaning of a window, press F1 for help. To see the inventory results of the life cycle of the wooden shed, go to Product Stages, Life cycle, Others and select Life cycle of the shed. Click the Analyze button **11**, then click Calculate, and click the Inventory tab.

## SimaPro (§

	Sort by Substance wi click on the h	Se th a eading	ect Invent!	ory	Show amo characteri per impac of the sele method	ounts or ized values t category ected		
S D:\SimaPro	Database\802 w803methods\P	rofessional: Tutorial and	h wood example -	[Analyze Life cy	(cle of the shed (2)]			
S File Edit	Calculate Tools Window	Heln		(,) <u>20</u> 2 c .)				
							_	
		.50 =	•••••••••••••••••••••••••••••••••••••••		<b>b</b>			
Network Tre	e Impact assessment Inventor	Y Process contribution	Setup   Checks (8	02,0) Product o	verview			
Compartment		r	C <u>u</u> t-off					
All compartme	nts 🖊 🗸 Amoun	t	• 0% ÷	🗌 Default un	iits		<u>⊪ %</u> ↓%↓	%
Per sub-con	mpartment Amount		🕞 standard	Exclude lo	ng-term			
🔲 Skip unused	Damage	terization e assessment	C Group	Per impact	category			
No Subst	tance / Normali Weighti	zation	Compartment	Unit	Total	Simple shed p	Waste scenario for shed	
1 1-But	anol	core	Air	нg	1.97	1.42	0.549	
2 1-But	anol		Water	hà	245	226	18.8	
3 1-Per	ntanol		Air	ng	489	447	41.2	
4 1-Per	ntanol		Water	μg	1.17	1.07	0.099	
5 1-Per	ntene		Air	hà	582	359	222	
6 1-Per	itene		Water	ng	886	811	74.8	
7 1-Pro	panol		Air	hà	13.6	10.8	2.74	
8 1-Pro	panol		Water	hà	4.58	4.21	0.366	
9 1,4-8	lutanediol		Air	hà	557	393	164	
10 1,4-0	incorrespond		Viater	pg	223	241	51.2	
11 2-Am	inopropanol		Water	ng	041	818	123	
12 2-Am	ene 2-methyl-		Air	ng	15	11.6	3 37	
14 2-But	tene, 2-methyl-		Water	00	35.9	27.8	8.09	
15 2-Met	thyl-1-propanol		Air	ng	633	568	65.1	
16 2-Met	thyl-1-propanol		Water	pd	1.52	1.36	0.156	
17 2-Met	thyl-4-chlorophenoxyacetic acid		Soil	hà	1.96	1.93	0.0313	
18 2-Nitr	robenzoic acid		Air	ng	156	134	22.1	
19 2-Pro	panol		Air	mg	3.67	3.02	0.653	
20 2-Pro	panol		Water	hà	9.93	8.75	1.18	
21 2,4-D	)		Air	hð	1.73	1.56	0.17	
22 2,4-D	)		Soil	рg	414	329	85.4	-
Analyzing 1 p 'Li	ife cycle of the shed'; Method: ReC	iPe Endpoint (H) V1.10 /	World ReCiPe H/A					

Figure 33: Inventory (LCI) result window

The Inventory window has many different features. For example, you can also use it to show characterized results. Using the right mouse click on the values gives you even more options to specify the results.

### 6.2 Impact Assessment (LCIA) results

In the same window you can quickly obtain the impact assessment results. Simply click the tab Impact assessment.

Figure 34 shows the Characterization result of the production of the Simple shed (in red) and the Waste scenario of the shed (in green). It is evident that production dominates some impact categories, while end-of-life dominates others.



Figure 34: Results of the characterization step. All impact scores are displayed on a 100% scale. The colors indicate the contribution of production and waste.

You can also calculate your results using another impact assessment method. To select a different method as your default, follow the three steps shown in the window below. We suggest you try different methods, and see if that would lead to different conclusions. The SimaPro database manuals give you an overview of the characteristics of the methods (see Help> Data Manuals > Database manual).

If you want to change a method, always copy the method to your project first (go to the Methods section in the LCA explorer, select the method you want to copy, press the copy button); make sure to rename this new method before saving it, and make your changes in the copied version. This will make sure you always have the original methods as a back-up.



Figure 35: Selecting an alternative impact assessment method

#### 6.2.1 Inspecting the complete network

You can get a complete view of a network by lowering the cut-off value to zero. You can produce a figure as shown below by setting the desired zoom level (parts of the tree may be outside the window) and using the Copy command under Edit (or CTRL+C). You can also use the Export command under File. SimaPro supports various formats, the BMP format works best with most software packages.

When the cut-off value is set to zero it is possible to analyze all of the processes, ranging from cutting the tree to the disposal processes. The 'thermometers' (the red bars on the right side of a box) show the contribution to the environmental load. The thickness of the line also indicates the total environmental load flowing between processes. While a red color means an environmental load, green means a negative environmental load, or in fact an environmental benefit.



Figure 36: Overview of the complete life cycle presented as a network (all processes shown, cut-off = zero)

#### 6.2.2 Inspecting the details

Finally we will show one of the most advanced features of the network presentation, the Show detail. By clicking the Show detail is button you can open a new window in which you get the specific results of the process you selected in the tree or network.

The box that you select determines the content of this window. For instance you can select the Planks process you used earlier. You can now see the contents of that record. You also see the inventory and impacts assessment results and the process contribution for the selected process. You can select every impact category indicator you want or present the LCI results in their original form.

In figure 37 we present the inventory results as characterized results for climate change.



Figure 37: Showing the details of a process in the tree

### 6.3 Contribution analysis

Often we do not only present the final results, but also want to show the contribution of different processes or different process groups. SimaPro has two important features to provide such a specification:

- 1. Process contribution: Specifies the contribution of each process. The impact of processes linked to each process is not taken into account.
- 2. Analysis of groups: Specifies the contribution of groups of processes, including the impact of processes linked to by processes in the group.

It is important to understand the differences between the two. Under Process contribution, you can only see processes that contain significant emissions or extractions from nature. SimaPro calculates this automatically. With the Analysis of groups function we also see the contribution of processes linked to the group. In the Analysis of groups function you can create your own groups, in which you can combine all kinds of similar processes, such as transport, energy, end-of-life and other processes.

#### Does a fridge pollute?

If you look at your fridge at home, there is no pollution. The electricity it uses does pollute. In a process contribution, one cannot see the fridge, as in the process that defines the fridge, there are no emissions. So even though the fridge is polluting, one does not see the fridge in the Process contribution itself. In the Analysis groups function you can see both the fridge and the electricity use. You can define your own groups and show the contribution of all processes that contribute to the environmental load of the fridge the way you want to show them.

#### 6.3.1 Process contribution analysis

To make a contribution analysis select your life cycle and click the Analyze button [][][]], or if you are presently in any other result window.

1. Select the tab Process contribution.

2. Click the Show chart button.

3. Adjust the cut-off to adjust the amount of processes shown in your chart.

In the figure below you can see that Steel contributes the most to the total impact of the life cycle, followed by electricity use. As previously mentioned, the Process contribution only takes into account the emissions and resource consumption that are specified in the process itself, not in the processes linked to that process. For instance we cannot see the assembly Simple shed.



Figure 38: Contribution analysis showing all processes in the network that contribute to the environmental impact of the shed. If the cut-off is adjusted to 1%, this contribution analysis will show all processes in the network that contribute more than 1%. The total contribution of the processes that are below the cut-off is then summarized in the column 'Remaining processes'.



#### 6.3.2 Analysis of Groups

While you are in the Network tab you can define groups of processes from which you want to see the contribution to the environmental load.



Figure 39: Selecting processes to include in a group, in this example all transport processes

The figure above show how a group of transport processes can be made. Please note that you only have to select the transport processes. The contribution of the underlying processes is automatically included. Once a group has been created, other groups can be added, as is shown in figure 40 below. A fourth group (Top) is always present and cannot be deleted. This group contains the contribution of all processes that do not belong to one of the other groups. SimaPro automatically calculates the processes that belong to this group. Note that you can select the top process to be part of a group, in that case the Top group will automatically disappear.



To remove processes from a group, click Remove and then select the processes to be removed.

Figure 40: Creation of two other groups: Electricity and Waste treatment

In this example, the Waste treatment group also links to some transport. In SimaPro this does not result in a double count. The Waste treatment group will not contain the impacts of transport, as these impacts are already in the transport group. The example shows that one must be careful when selecting groups, as such combinations often exist.

With the groups defined, we can return to the Inventory or Impact Assessment results page. You will see a clear overview of the contribution from each group you defined, in addition to the Top group.





Figure 41: Impact assessment per group

Instead of a Standard specification in which one sees the contribution of the underlying processes, we can now choose to view the contribution of each group (figure 41). This specification also works in the Characterization, Normalization and other views, as well as in the Inventory results.

Please note that the Analysis of groups feature does not work in a looped data structure, such as that in input output databases and the unit versions of the ecoinvent data libraries. This is because in such a looped structure it is simply not clear where the contribution of underlying processes ends: everything can be linked to everything. To use the feature with looped datasets, you need to use the equivalent system processes.

If you use mixed data (looped and non-looped), grey edges around processes indicate which processes are looped and cannot be used in groups.

#### Analysis groups for EPD's

The Analysis of groups is a powerful tool when you create Environmental Product Declarations or EPDs. The methodology to make EPDs is defined in the ISO 14025 standard. A further specification of how you should make an EPD is specified in a Product Category Rule document (PCR). A list of available PCRs can be found on www.environdec.com. An important requirement in many EPDs is to specify the contribution of transport, waste, and sometimes energy. With the Analysis of groups function you can easily supply these. See also the 'Introduction to LCA with SimaPro' manual.

## 7 Lesson 2e: Using Parameters for Sensitivity Analysis

Overview	
What you will learn	How to use parameters to automatically switch between allocation principles
Required entry level	Lesson 2a, 2b, 2c and 2d should be completed first. If you have skipped 2b and used a standard waste scenario the results will be different from the results in this tutorial.
Recommended reading	'Introduction to LCA with SimaPro', chapters 4 and 5
Project needed	Tutorial with wood example
Approximate time needed	45-60 minutes

Parameters can be used for many purposes, like developing alternative scenarios or a modular process structure in which you can include or exclude parts of the life cycle.

### 7.1 The impact of the allocation principle

In section 3.4.1 we chose the mass allocation principle for 3 outputs of a sawmill: planks, sawdust and bark. We discussed different allocation percentages, based on mass and economic allocation. Switching between two types of allocation can of course be done by manually changing the allocation percentages, but you can also create a "switch" using parameters. The benefit of using parameters is that it becomes easy to see how important the effect of the allocation choice is.

Below we show how you can redefine the process record with the planks. In the new version, you can change the allocation basis by simply changing a parameter.

There are many ways to define parameters, but in the example below we will define an input parameter "use\_econ\_all". If this input parameter is equal to one, it means we want to use economic allocation. If it is set to zero, it means we want to use mass allocation. We also define a calculated parameter called "use\_mass\_all". This parameter is calculated by SimaPro using the formula: use\_mass\_all =  $1 - use_econ_all$ .

This simple formula lets the mass allocation parameter become equal to one if the economic allocation is assigned the value zero, and vice versa.

To define these parameters, please reopen the process that defines the planks, sawdust and bark. Click the Parameters tab and enter the formulas as shown in the next figure. (Please note that this feature is not available in the Compact, Classroom and Faculty licenses of SimaPro.)

7



Figure 42: Defining an input parameter and a calculated parameter

Return to the input/output section by clicking the Input/output tab. Instead of using fixed percentages for allocation, you can now enter three other formulas. These reflect the economic (80, 20, 0%) and mass (50, 40, 10%) allocation percentages.

For the allocation percentage for planks, enter: 80\*use\_econ\_all+50\*use\_mass\_all

If you set use\_econ\_all to one, the allocation percentage will become equal to 80%, if you set use\_econ\_all to zero, the value for use\_mass\_all will become one, which means the allocation percentage will become equal to 50%. For the allocation of sawdust you can enter a similar formula, as shown below. For the allocation to bark you can create a simpler formula, since for economic allocation the allocation percentage is zero.

	Do 80 <sup>0</sup> do	not enter %'; SimaPr this for yo	'= ro wi pu	I				
Edit material process 'Planks'								
Documentation Input/output Parameters System of	description							
Known outputs to technosphere. Products and co-pro	ducts			Proc	ducts			
Name	Amount	Unit	Quantit	y	Allocation %			Waste type
Planks	500	kg	Mass		80*use_econ_all	+50*use_mass_all =	= 80%	Wood
Sawdust	400	kg	Mass		20*use_econ_all-	+40*use_mass_all =	= 20%	Wood
Bark	100	kg	Mass		10*use_mass_all	= 0%		Wood
(Insert line here)								
Known outputs to technosphere. Avoided products Name				Amount	Unit	Distribution	SD^2 or 2	*SD Min
(Insert line here	)							
				Inp	outs			
Known inputs from nature (resources) Name (Insert line here)		Sub-compart	tment	Amount	Unit	Distribution	SD^2 or 2	*SD Min
Known inputs from technosohere (materials/fuels)								Þ

Figure 43: Using parameters to calculate allocation percentages

### 7.2 Comparing the impact of alternative allocation principles

SimaPro has a powerful feature that allows you to compare between two parameter settings. We will now use this feature to compare the differences in environmental load between the two allocation principles.

While you have the Planks process selected, click Compare 1. A calculation setup box will appear. At the top, there are three tabs. Please select the Parameter sets tab in the middle. A window like the one below will appear; simply follow the steps.



Figure 44: Creation of two parameter sets

Next a new screen will appear, from which you can select the parameter you want to use.

	The comment field displays the comment added when you define the parameter	you ed	Click Scan Tree; SimaPro will list the available parameters	
ら Select Paramete	r /			×
No Parameter / 1 use_econ_all	Type De Process Pla	efined in <mark>anks</mark>	Value 1	Select
				Cancel
If value equals 1, ec values may not be us	onomic allocation is applied. If ( sed.	0, mass a	llocation is applied. Other	
			-	

Figure 45: Selecting the parameter you want to use in the comparison

After you click Select a new line is added. For clarification, you should now edit the default names Set 1 and Set 2 at the left-hand side of the box into something more representative (for example, economic allocation and mass allocation). You will see that these names will now appear as headings of the columns on the right-hand side.

Step 1 param double	: Rename the neter sets by e-clicking them	Step 2: Give values for e principle	e the different ach allocation		
S New calculation setup					
General Parameter sets Analys	sis groups Chart options				
Import from Excel sheet			/ /	x	
No Parameter set	No Parameter De	efined in	Type econ	omic alloci mass allocatior	
1 economic allocation	1 use_econ_all Pla	lanks F	Process 1	► 0	
2 mass allocation /	If value equals 1, economic may not be used.	c allocation is applied.	If 0, mass allocation i	is applied. Other values	
<u>A</u> dd <u>D</u> elete	Add <u>parameter</u> Delete p	parameter 🗌	Refresh	View import log	
Help			Ģ	Calculate Close	

Figure 46: Setting different values for each parameter set



Next click Calculate. In the Impact assessment tab, under Characterization, you will see a comparison of the environmental load of plank production with economic and with mass allocation, as seen in the screen below.

Figure 47: Result of the comparison between parameter sets. The red bars reflect the impact category indicator scores when economic allocation is used; the green when mass allocation is used. In this example we use characterization. The vertical axis is a percentage scale

The graph shows a comparison between the impacts of a plank using economic and mass allocation. The highest score is scaled to 100% and the lowest is a relative score. In this simple case the difference between all scores is a fixed percentage of 62.5%, as the allocation factor influences all impacts in the same way. In a complex process tree with many allocated processes the result will be different, and it is precisely in these situations where parameterized allocation is extremely powerful.

Another application of using parameters is to create switches that influence the system boundaries. For instance you could make a switch that determines if the growing of the tree should become part of your LCA. In that case you may want to subtract the  $CO_2$  absorbed in the wood. Likewise, you can set a switch to include or exclude benefits (avoided products), such as gas collection from landfills.

#### Using parameters to compare alternative shed designs

In section 5.3 we demonstrated how you can parameterize the dimensions of the shed. We can use the same principle to compare two or more shed designs using different parameters. If you have made the parameterized set according to the instructions in section 5.3 you can define a calculation set-up box as shown below.



As you can see, the parameter for the allocation (last line) is also among the parameters you may want to change.

#### Advanced features of parameters: linking processes to excel or other data sources

This advanced feature is only available in SimaPro Developer, and cannot be seen in the demo. In SimaPro Developer, you can link each process record to an MS Excel spreadsheet or an SQL database. This opens up many possibilities. For instance, if you use Excel for data collection, you can ask each data provider to enter data in a certain format in an SQL database or a spreadsheet, and this can automatically update your LCA.

The illustrations below give an example. The Excel datasheet is directly linked to from within a spreadsheet.

4	А	В	С					
1	Location: Ams	terdam						
2								
3	electricity	134	MWh					
4	CO2	7	ton					
5	SO2	77	kg					
6	NOx	13	kg					
Kn	own inputs from	technosp	here (ele	ectr	icity/heat)			
Na	ime	Amo	unt			Unit	Distrib	(SD^2
Ele	Electricity, low voltage C:\Data collection 2012\[Data Amsterdam (v1.1).xlsx]Sheet1'!B3 = 134 MWh							
	(Insert line here	)						
					C	outputs		
_								
Em	nissions to air							
Na	ime	Sub	o-co Amou	unt			Unit	D
Ca	arbon dioxide		'C:\D	)at	a collection 2012\[Data Amsterdam (v1.1).xlsx]Sheet1'!B4 =	- 7	ton	-
Su	Ilfur dioxide		'C:\D	)at	a collection 2012\[Data Amsterdam (v1.1).xlsx]Sheet1'!B5 =	- 77	kg	
Ni	trogen oxides		'C:\D	)at	a collection 2012\[Data Amsterdam (v1.1).xlsx]Sheet1'!B6 =	= 13	kg	
	(Insert line here	e)						
_				_				

# 8 Lesson 3: Building Sophisticated Product Stages using the Wizard

Overview	
What you will learn	This exercise shows you how to use the LCA wizard tools in SimaPro to model complex end-of-life scenarios. In fact in a much shorter time than you needed for lesson 2c on waste scenarios.
Required entry level	We recommend doing this lesson after you have done the lesson 2c, but it is also possible to start this lesson after lesson 1.
Recommended reading	'Introduction to LCA with SimaPro'. Chapter 8 gives provides some background; it is recommended, but not essential to read it.
Project needed	Introduction to SimaPro. Please make sure that the methods library and the Industry data library are selected under "libraries"
Approximate time needed	30-45 minutes

### 8.1 The problem

Due to the increase in digitalizing information by email, USB and MP3s, people are expected to start disposing of their CD-ROMs. Does it make sense (from an environmental point of view) to organize a special recycling system? For this, we need to compare two product systems, one with the normal Dutch disposal scenario (landfill and incineration mix), and one without the recycling system.

### 8.2 The SimaPro solution

Use the LCA wizard to model two product systems, one with recycling and one with the average disposal scenario in the Netherlands. The functional unit is one CD-ROM. For this example, some simplifications are made in the logistics system and some small parts of the CD-ROM are left out. There is also no need to define the complete production process; only the material content is important.

#### 8.2.1 Product system without recycling

Open the project 'Introduction to SimaPro'. Start the LCA wizard and define one assembly and associated life cycle with the following materials:

15 gram

1 gram

105 gram

- 1. Polyvinylchloride, at regional storage/RER S demo 7
- 2. Aluminium, production mix, at plant/RER S demo 7
- 3. Polypropylene granulate at plant/RER S demo 7
- 4. Do not enter processes in the assembly or life cycle
- 5. Select Municipal/NL S demo7 as the waste scenario

You will need 22 steps in the wizard. After finishing the wizard, save the product stages and the product system.

67

## SimaPro 🗳

#### Detailed instructions

If the generic d	escription above is not clear enough, you can follow the detailed instructions below:
Start the LCA v	Vizard
Step 1:	Click: Next.
Step 2:	Select Assembly and life cycle.
Step 3:	Select Assembly.
Step 4:	Enter CD-ROM without recycling.
Step 5:	Enter 1, indicating that the functional unit is just one CD-ROM.
Step 6:	Yes, enter materials.
Step 7:	Select Plastics.
Step 8:	Select Polyvinylchloride, at regional storage/RER S demo 7; this is the main material for the CD-ROM.
Step 9:	Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg.
Step 11 to 17:	Now add the material for thin layer on the CD-ROM, which is the metal aluminum or Aluminium, production mix at plant/RER S demo 7. Enter 1 gram as amount. Add the CD-ROM case which consists of 105 gram polypropylene granulate at plant/RER S demo 7 (material type: plastics).
Step 18:	This assembly is ready, you have now entered the main materials.
Step 19:	Although the CD-ROM will use energy to play, we leave this aspect out of the comparison, as both for the recycled and non-recycled CD-ROM these impacts will not differ, so choose No processes in the life cycle.
Step 20:	Yes, we will enter a waste scenario.
Step 21:	Select Municipal waste/NL S demo 7; this scenario contains all information on what percentages are land filled, incinerated and recycled (see also the tree in the background).
Step 22:	No additional life cycles.
After step 22:	Please confirm that you want to save the product system. Give the product system a name such as CD-ROM without recycling

#### 8.2.2 Product system with recycling

Defining this product system is somewhat more complex. You will need 44 steps. The key issue is to make SimaPro understand that the CD-ROM and the case have different disposal scenarios and that there is a disassembly step. To achieve this, you must define an assembly with two subassemblies, one called CD-ROM only and one called Case only. The LCA wizard is slightly counter intuitive since when you define a subassembly, it first asks about the disposal of the subassembly, and after you entered this it will ask about what is actually in the assembly.

Start the LCA wizard, but this time enter in step 3 that you want to work with subassemblies, and confirm you will work with a Disposal model in step 4.

- 1. Define a main assembly called CD-ROM with recycling, and choose Incineration/CH S demo7. Specify that 100% of the waste is sent to disassembly. Do not add materials or processes, but create a subassembly in step 11.
- 2. Specify the name CD-ROM only for the first subassembly, specify Incineration/CH S demo7 and specify that 100% of the CD-ROMs go to this waste scenario. Now specify that the CD-ROM contains 15 gram Polycarbonate (use Polyvinylchloride, at regional storage/RER S demo 7, and 1 gram aluminum (use Aluminium, production mix, at plant/RER S demo 7).
- 3. Create a new subassembly (step 26) for the case. Specify Recycling only avoided demo7, and again specify 100% is sent to this waste scenario (in SimaPro recycling is also seen as one of the waste scenarios). Now specify 105 gram high impact polypropylene (use polypropylene granulate at plant/RER S demo 7) for the case.
- 4. For the collection process, add Transport, van <3.5t/RER S demo7 to the life cycle in step 40 and 41, and add 0.02 tkm as transport amount (the weight of the CD-ROM is 121 grams, which is multiplied by the average transport distance 200 km, the rounded value is thus 0.024 tkm).

You will need 44 steps in the wizard. After finishing the wizard, save the product stages and the product system.

If the generic description above is not clear enough, you can follow the detailed instructions below: Start the LCA wizard Step 1: Click Next. Step 2: Select Assembly and life cycle. Step 3: Select Assembly with Subassembles. Step 4: Select Disposal. Step 5: Enter the name of the assembly: CD-ROM with recycling. Step 6: Enter 1. Now, and this seems a bit counter intuitive, the Wizard first wants you to specify how the CD-ROM is disposed of. Step 7: Select Incineration/CH S demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy. Step 8: Enter 100% in the field Disassembly. Indicating that all CD-ROMs are sent to disassembly. Step 9: Click Next. Step 10: Read and click Next. Now SimaPro finally wants to know which materials are in the CD-ROM. Step 12: Enter name: CD-ROM only. Step 14: Select Incineration/CH S demo7. Indicating that all CD-ROM will be incinerated. Step 12: Enter name: CD-ROM only. Step 14: Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated. Step 15: Enter 1. Step 16: Click Next. Step 17: Yes, enter materials. Step 18: Select Polyon in the field for subassembly be step 44: Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated. Step 19: Select Polyon just selected (incineration). Step 16: Click Next. Step 17: Yes, enter materials. Step 19: Select PolyonyloyIche at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can a flauminum, production mix at plant/RER S demo 7 in the same way. Step 20: Enter 1. Step 21: Enter 1. Step 21: Select PolyonyloyIche at regional storage/RER S demo 7 in the same way. Step 24: Select PolyonyloyIche at regional storage/RER S demo 7. This is the main material for the CD-ROM (you can 6 Aluminum, production mix at plant/RER S demo 7 in the same way. Step 25: No, This subassembly is ready. Step 26: Enter 1. Step 27: Enter 1. Step 27: Enter 1. Step 29: Choose Recycling only avoided demo7. Step 30: Enter 1. Step 31: Click Next. Now SimaPro finally	Detailed instructions for the CD-ROM recycling product system				
<ul> <li>Stat The LCA wizard</li> <li>Step 1: Click Next.</li> <li>Select Assembly with Subassemblies.</li> <li>Step 3: Select Assembly with Subassemblies.</li> <li>Step 4: Select Assembly CD-ROM with recycling.</li> <li>Step 5: Enter the name of the assembly: CD-ROM with recycling.</li> <li>Step 6: Enter 1.</li> <li>Now and this seems a bit counter intuitive, the Wizard first wants you to specify how the CD-ROM is disposed of.</li> <li>Step 7: Select Incineration/CH S demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy.</li> <li>Step 8: Enter 100% in the field Disassembly. Indicating that all CD-ROMs are sent to disassembly.</li> <li>Step 9: Click Next.</li> <li>Step 10: Read and click Next.</li> <li>Now simaPro finally wants to know which materials are in the CD-ROM.</li> <li>Step 12: Enter name: CD-ROM only.</li> <li>Step 13: Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.</li> <li>Step 14: Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.</li> <li>Step 15: Enter 1.</li> <li>Step 16: Click Next.</li> <li>Step 16: Click Next.</li> <li>Step 17: Yes, enter materials.</li> <li>Step 18: Select Polyviny/choride, at regional storage/RER S demo 7. this is the main material for the CD-ROM will see that in the tree, not only the material and change this later in the product system (see below).</li> <li>Step 20: Enter the mass of the CD-ROM, in this case 15 gram, or 0015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 7 gram of Alumnium, production mix at plant/RER S demo 7. This is the main material for the CD-ROM will be tablesembly.</li> <li>Step 20: Enter 1.</li> <li>Step 21: Chrose Recycling only avoided demo7.</li> <li>Step 23: Enter 1.</li> <li>Step 24: Enter 1.</li> <li>Step 25: No, This subassembly is ready.</li> <li>Step 26: Enter 1.</li> <li>Step 27: Enter Case only as name for the subassembly.</li> <l< td=""><td>If the generic c</td><td>lescription above is not clear enough, you can follow the detailed instructions below:</td></l<></ul>	If the generic c	lescription above is not clear enough, you can follow the detailed instructions below:			
Step 1:       Click Next.         Step 2:       Select Assembly and life cycle.         Step 3:       Select Disposal.         Step 4:       Select Disposal.         Step 5:       Enter the name of the assembly: CD-ROM with recycling.         Step 6:       Enter 1.         Now, and this seems a bit counter intuitive, the Wizard first wants you to specify how the CD-ROM is disposed of.         Step 7:       Select incineration/CH S demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy.         Step 8:       Enter 100% in the field Disassembly indicating that all CD-ROMs are sent to disassembly.         Step 9:       Click Next.         Now SimaPro finally wants to know which materials are in the CD-ROM.         Step 11:       Now create a subassembly. This is the first subassembly we create.         Step 12:       Enter 100% on the field to rubassemblies send to waste, indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 13:       Enter 1.         Step 14:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 100% in the field to rubassemblies send to waste, indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 14:       Select Paistics.         Step 15:       Click Next. <t< td=""><td>Start the LCA v</td><td>vizard</td></t<>	Start the LCA v	vizard			
Step 2:       Select Assembly and life cycle.         Step 4:       Select Assembly with Subassemblies.         Step 4:       Select Disposal.         Step 5:       Enter 1.         Now, and this seems a bit counter intuitive, the Wizard first wants you to specify how the CD-ROM is disposed of.         Step 7:       Select Incineration/CH 5 demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy.         Step 8:       Enter 100% in the field Disassembly. indicating that all CD-ROMs are sent to disassembly.         Step 9:       Click Next.         Now wimPro finally wants to know which materials are in the CD-ROM.         Step 12:       Enter name: CD-ROM only.         Step 13:       Enter 1.         Now create a subassembly. This is the first subassembly we create.         Step 14:       Select PACMOM only.         Step 15:       Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 15:       Enter 100% in the field for subassemblies.         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Plastics.         Step 19:       Select Plastics.         Step 19:       Select Plastics.         Step 19:       S	Step 1:	Click Next.			
Step 3:       Select Assembly with Subassemblies.         Step 4:       Select Disposal.         Step 5:       Enter the name of the assembly: CD-ROM with recycling.         Step 6:       Enter 1.         Now, and this seems a bit counter intuitive, the Wizard first wants you to specify how the CD-ROM is disposed of.         Step 7:       Select Incineration/CH S demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy.         Step 8:       Enter 100% in the field Disassembly, indicating that all CD-ROMs are sent to disassembly.         Step 9:       Click Next.         Now Greate a subassembly. This is the first subassembly we create.         Step 11:       Now create a subassembly. This is the first subassembly we create.         Step 12:       Enter nome: CD-ROM only.         Step 13:       Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 14:       Select Incineration/CH 5 demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 16:       Click Next         Step 17:       Yes, enter materials.         Step 18:       Select Polyviny(chloride, at regional storage/RER 5 demo 7, this is the main mate	Step 2:	Select Assembly and life cycle.			
Step 4:       Select Disposal.         Step 5:       Enter the name of the assembly: CD-ROM with recycling.         Step 6:       Enter 1.         Now, and this seems a bit counter intuitive, the Wizard first wants you to specify how the CD-ROM is disposed of.         Step 7:       Select Iniciparation/CH 5 demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy.         Step 8:       Enter 100% in the field Disassembly. indicating that all CD-ROMs are sent to disassembly.         Step 9:       Click Next.         Now SimaPro finally wants to know which materials are in the CD-ROM.         Step 11:       Now Create a subassembly. This is the first subassembly we create.         Step 12:       Enter name: CD-ROM only.         Step 13:       Enter 1.         Step 14:       Select Incineration/CH 5 demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 1.         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Polyvinylchloride, at regional storage/RER 5 demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).         Step 26:       Yes add another subassembly.         Step 19:       Select Polyvinylchloride, at regional storage/RER 5 demo 7, this is the main material for the CD-ROM (you can a	Step 3:	Select Assembly with Subassemblies.			
Step 5:       Enter the name of the assembly: CD-ROM with recycling.         Step 6:       Enter 1.         Now, and this seems a bit counter intuitive, the Wizard first wants you to specify how the CD-ROM is disposed of.         Step 7:       Select Incineration/CH S demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy.         Step 8:       Enter 100% in the field Disassembly, indicating that all CD-ROMs are sent to disassembly.         Step 9:       Click Next.         Now create a subassembly. This is the first subassembly we create.         Step 11:       Now create a subassembly. This is the first subassembly we create.         Step 12:       Enter name: CD-ROM only.         Step 13:       Enter 1.         Step 14:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 1.0% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Plastics.         Step 19:       Select Plastics.         Step 10:       Enter 1.0%         Step 20:       Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and	Step 4:	Select Disposal.			
Step 6:       Enter 1.         Now, and this seems a bit counter intuitive, the Wizard first wants you to specify how the CD-ROM is disposed of.         Step 7:       Select Incineration/CH S demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy.         Step 8:       Enter 100% in the field Disassembly, indicating that all CD-ROMs are sent to disassembly.         Step 9:       Click Next.         Step 10:       Read and click Next.         Now SimaPro finally wants to know which materials are in the CD-ROM.         Step 12:       Enter name: CD-ROM only.         Step 13:       Enter 1.         Step 14:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 1.         Step 16:       Enter 1.         Step 17:       Yes, enter materials.         Step 18:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 17:       Yes, enter materials.         Step 18:       Select Polyinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).         Step 20:       Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg, Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add I gram of Alum	Step 5:	Enter the name of the assembly: CD-ROM with recycling.			
Now, and this seems a bit counter intuitive, the Wizard first wants you to specify how the CD-ROM is disposed of.         Step 7:       Select Incineration/CH S demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy.         Step 8:       Enter 100% in the field Disassembly, indicating that all CD-ROMs are sent to disassembly.         Step 9:       Click Next.         Step 10:       Read and click Next.         Now SimaPro finally wants to know which materials are in the CD-ROM.         Step 12:       Enter name: CD-ROM only.         Step 13:       Enter 1.         Step 14:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Plastics.         Step 19:       Select Plastics.         Step 20:       Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, ent only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1 gram of Aluminjum, production mix at plant/RER 5 demo 7 in the same way.         Step 25:       No, This subassembly.       Step 26. Yes add another subassembly.         Step 27:	Step 6:	Enter 1.			
Step 7:       Select Incineration/CH S demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy.         Step 8:       Enter 100% in the field Disassembly, indicating that all CD-ROMs are sent to disassembly.         Step 10:       Read and click Next.         Now SimaPro finally wants to know which materials are in the CD-ROM.         Step 11:       Now create a subassembly. This is the first subassembly we create.         Step 12:       Enter name: CD-ROM only.         Step 13:       Enter 1.         Step 14:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 1.         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 19:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Polyvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM up (you can also select another material and change this later in the product system (see below).         Step 20:       Select Polyvinylchloride, at regional storage/RER S demo 7 in the same way.         Step 219:       Select Polyvinylchloride,		Now, and this seems a bit counter intuitive, the Wizard first wants you to specify how the CD-ROM is disposed of.			
Step 8:       Enter 100% in the field Disassembly, indicating that all CD-ROMs are sent to disassembly.         Step 9:       Click Next.         Step 10:       Read and click Next.         Now SimaPro finally wants to know which materials are in the CD-ROM.         Step 11:       Now create a subassembly. This is the first subassembly we create.         Step 12:       Enter name: CD-ROM only.         Step 13:       Enter 1.         Step 14:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Plastics.         Step 19:       Select Plastics.         Step 20:       Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1 gram of Aluminium, production mix at plant/RER S demo 7 in the same way.         Step 26:       Yes add another subassembly.         Step 27:       Enter Case only as name for the subassembly.         Step 28:       No, This subassembly is ready.         Step 30:       Enter 1.         Step 30:	Step 7:	Select Incineration/CH S demo7. This waste scenario has all data on the incineration of waste, including the reclamation of energy.			
Step 9:       Click Next.         Step 10:       Read and click Next.         Now SimaPro finally wants to know which materials are in the CD-ROM.         Step 11:       Now create a subassembly. This is the first subassembly we create.         Step 12:       Enter name: CD-ROM only.         Step 13:       Enter 1.         Step 14:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 1.         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Plastics.         Step 19:       Select Plastics.         Step 19:       Select Ployinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).         Step 20:       Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1 gram of Aluminium, production mix at plant/RER S demo 7 in the same way.         Step 26:       Yes add another subassembly.         Step 27:       Enter Case only as name for the subassembly.         Step 30:       Enter 1.         Step 31:       Click Next.         Now SimaPro finally wants to know which materials are in the cases.<	Step 8:	Enter 100% in the field Disassembly, indicating that all CD-ROMs are sent to disassembly.			
Step 10:       Read and click Next. Now SimaPro finally wants to know which materials are in the CD-ROM.         Step 11:       Now create a subassembly. This is the first subassembly we create.         Step 12:       Enter name: CD-ROM only.         Step 13:       Enter 1.         Step 14:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Polyvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).         Step 20:       Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1 gram of Aluminium, production mix at plant/RER S demo 7 in the same way.         Step 25:       No, This subassembly is ready.         Step 26:       Yes add another subassembly.         Step 29:       Choose Recycling only avoided demo7.         Step 30:       Enter 1.         Step 31:       Click Next.         Now SimaPro finally wants to know which materials are in the cases.	Step 9:	Click Next.			
Now SimaPro finally wants to know which materials are in the CD-ROM.Step 11:Now create a subassembly. This is the first subassembly we create.Step 12:Enter name: CD-ROM only.Step 13:Enter 1.Step 14:Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.Step 15:Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).Step 16:Click Next.Step 17:Yes, enter materials.Step 18:Select Plastics.Step 19:Select Polyvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).Step 20:Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now 	Step 10:	Read and click Next.			
Step 11:       Now create a subassembly. This is the first subassembly we create.         Step 12:       Enter name: CD-ROM only.         Step 13:       Enter 1.         Step 14:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 19:       Select Plastics.         Step 20:       Enter the mass of the CD-ROM in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1 gram of Aluminium, production mix at plant/RER S demo 7 in the same way.         Step 25:       No, This subassembly.         Step 26:       Yes add another subassembly.         Step 29:       Enter Case only as name for the subassembly.         Step 29:       Choose Recycling only avoided demo7.         Step 31:       Click Next.         Now SimaPro finally wants to know which materials are in the cases.         Step 32:       Yes, enter materials.         Step 33:       Select Plastics.         Step 34:       Select Plastics.         Step 25:       No, This subassembly is ready. <td></td> <td>Now SimaPro finally wants to know which materials are in the CD-ROM.</td>		Now SimaPro finally wants to know which materials are in the CD-ROM.			
Step 12:Enter name: CD-ROM only.Step 13:Enter 1.Step 14:Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.Step 15:Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).Step 16:Click Next.Step 17:Yes, enter materials.Step 18:Select Plastics.Step 19:Select Plastics.Step 20:Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1gram of Aluminium, production mix at plant/RER S demo 7 in the same way.Step 26:Yes add another subassembly.Step 27:Enter Case only as name for the subassembly.Step 28:Enter 1.Step 29:Choose Recycling only avoided demo7.Step 31:Click Next.Now SimaPro finally wants to know which materials are in the cases.Step 32:Yes, enter materials.Step 33:Select Plastics.Step 34:Select Plastics.Step 35:Enter 1.Step 36:The materials.Step 37:Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).Step 31:Click Next. Now SimaPro finally wants to know which materials are in the cases.Step 33:Select Plastics.Step 34:Select Plastics.Step 35:Enter the mass of the case, in this case 105 gram, or 0.105 kg. <td>Step 11:</td> <td>Now create a subassembly. This is the first subassembly we create.</td>	Step 11:	Now create a subassembly. This is the first subassembly we create.			
Step 13:Enter 1.Step 14:Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.Step 15:Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).Step 16:Click Next.Step 17:Yes, enter materials.Step 18:Select Plastics.Step 19:Select Polyvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).Step 20:Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1gram of Aluminium, production mix at plant/RER S demo 7 in the same way.Step 25:No, This subassembly is ready.Step 26:Yes add another subassembly.Step 27:Enter 1.Step 30:Enter 1.Step 31:Click Next. Now SimaPro finally wants to know which materials are in the cases.Step 32:Yes, enter materials.Step 33:Select Plastics.Step 34:Select Playropylene granulate at plant/RER S demo 7. This is the main material for the case.Step 35:Finter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).Step 31:Click Next. Now SimaPro finally wants to know which materials are in the cases.Step 33:Select Plastics.Step 34:Select Plastics.Step 35:Enter the mass of	Step 12:	Enter name: CD-ROM only.			
Step 14:       Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.         Step 15:       Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Plastics.         Step 19:       Select Polyvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).         Step 20:       Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1 gram of Aluminium, production mix at plant/RER S demo 7 in the same way.         Step 25:       No, This subassembly is ready.         Step 27:       Enter Case only as name for the subassembly.         Step 28:       Enter 1.         Step 29:       Choose Recycling only avoided demo7.         Step 30:       Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).         Step 31:       Click Next.         Now SimaPro finally wants to know which materials are in the cases.         Step 33:       Select Plastics.         Step 34:       Select Plastics.         S	Step 13:	Enter 1.			
Step 15:       Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).         Step 16:       Click Next.         Step 17:       Yes, enter materials.         Step 18:       Select Plastics.         Step 19:       Select Polyvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).         Step 20:       Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1 gram of Aluminium, production mix at plant/RER S demo 7 in the same way.         Step 25:       No, This subassembly.         Step 27:       Enter Case only as name for the subassembly.         Step 28:       Enter 1.         Step 29:       Choose Recycling only avoided demo7.         Step 30:       Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).         Step 31:       Click Next.         Now SimaPro finally wants to know which materials are in the cases.         Step 33:       Select Plastics.         Step 34:       Select Plastics.         Step 35:       Enter the mass of the case, in this case 105 gram, or 0.105 kg.         Step 36:       Th	Step 14:	Select Incineration/CH S demo7. Indicating that the CD-ROM will be incinerated.			
Step 16:Click Next.Step 17:Yes, enter materials.Step 18:Select Plastics.Step 19:Select Ployvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).Step 20:Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1 gram of Aluminium, production mix at plant/RER S demo 7 in the same way.Step 25:No, This subassembly is ready.Step 26:Yes add another subassembly.Step 27:Enter Case only as name for the subassembly.Step 28:Enter 1.Step 29:Choose Recycling only avoided demo7.Step 30:Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).Step 31:Click Next. Now SimaPro finally wants to know which materials are in the cases.Step 33:Select Plastics.Step 34:Select Ploypropylene granulate at plant/RER S demo 7. This is the main material for the case.Step 35:Enter the mass of the case, in this case 105 gram, or 0.105 kg.Step 36:The Subassembly is ready.	Step 15:	Enter 100% in the field for subassemblies send to waste; indicating that all CD-ROMs are sent to the waste scenario you just selected (incineration).			
Step 17:Yes, enter materials.Step 18:Select Plastics.Step 19:Select Ployvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).Step 20:Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1 gram of Aluminium, production mix at plant/RER S demo 7 in the same way.Step 25:No, This subassembly is ready.Step 26:Yes add another subassembly.Step 27:Enter Case only as name for the subassembly.Step 28:Enter 1.Step 29:Choose Recycling only avoided demo7.Step 29:Choose Recycling only avoided demo7.Step 31:Click Next. Now SimaPro finally wants to know which materials are in the cases.Step 32:Yes, enter materials.Step 33:Select Plastics.Step 34:Select Plastics.Step 35:Enter the mass of the case, in this case 105 gram, or 0.105 kg.Step 36:The Subassembly is ready.	Step 16:	Click Next.			
Step 18:Select Plastics.Step 19:Select Polyvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).Step 20:Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1gram of Aluminium, production mix at plant/RER S demo 7 in the same way.Step 25:No, This subassembly is ready.Step 26:Yes add another subassembly.Step 27:Enter Case only as name for the subassembly.Step 28:Enter 1.Step 29:Choose Recycling only avoided demo7.Step 30:Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).Step 31:Click Next. Now SimaPro finally wants to know which materials are in the cases.Step 33:Select Plastics.Step 34:Select Plastics.Step 34:Select Plastics.Step 35:Enter the mass of the case, in this case 105 gram, or 0.105 kg.Step 36:The Subassembly is ready.	Step 17:	Yes, enter materials.			
<ul> <li>Step 19: Select Polyvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).</li> <li>Step 20: Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1gram of Aluminium, production mix at plant/RER S demo 7 in the same way.</li> <li>Step 25: No, This subassembly is ready.</li> <li>Step 26: Yes add another subassembly.</li> <li>Step 27: Enter Case only as name for the subassembly.</li> <li>Step 28: Enter 1.</li> <li>Step 29: Choose Recycling only avoided demo7.</li> <li>Step 30: Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).</li> <li>Step 31: Click Next. Now SimaPro finally wants to know which materials are in the cases.</li> <li>Step 32: Yes, enter materials.</li> <li>Step 33: Select Plastics.</li> <li>Step 34: Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.</li> <li>Step 35: Enter the mass of the case, in this case 105 gram, or 0.105 kg.</li> <li>Step 36: The Subassembly is ready.</li> </ul>	Step 18:	Select Plastics.			
<ul> <li>Step 20: Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1gram of Aluminium, production mix at plant/RER S demo 7 in the same way.</li> <li>Step 25: No, This subassembly is ready.</li> <li>Step 26: Yes add another subassembly.</li> <li>Step 27: Enter Case only as name for the subassembly.</li> <li>Step 28: Enter 1.</li> <li>Step 29: Choose Recycling only avoided demo7.</li> <li>Step 30: Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).</li> <li>Step 31: Click Next. Now SimaPro finally wants to know which materials are in the cases.</li> <li>Step 32: Yes, enter materials.</li> <li>Step 33: Select Plastics.</li> <li>Step 34: Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.</li> <li>Step 35: Enter the mass of the case, in this case 105 gram, or 0.105 kg.</li> <li>Step 36: The Subassembly is ready.</li> </ul>	Step 19:	Select Polyvinylchloride, at regional storage/RER S demo 7, this is the main material for the CD-ROM (you can also select another material and change this later in the product system (see below).			
<ul> <li>Step 25: No, This subassembly is ready.</li> <li>Step 26: Yes add another subassembly.</li> <li>Step 27: Enter Case only as name for the subassembly.</li> <li>Step 28: Enter 1.</li> <li>Step 29: Choose Recycling only avoided demo7.</li> <li>Step 30: Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).</li> <li>Step 31: Click Next. Now SimaPro finally wants to know which materials are in the cases.</li> <li>Step 33: Select Plastics.</li> <li>Step 34: Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.</li> <li>Step 35: Enter the mass of the case, in this case 105 gram, or 0.105 kg.</li> <li>Step 36: The Subassembly is ready.</li> </ul>	Step 20:	Enter the mass of the CD-ROM, in this case 15 gram, or 0.015 kg. Note that you will see that in the tree, not only the material is added, but also the waste scenario and waste treatment for PVC. Now add 1gram of Aluminium, production mix at plant/RER S demo 7 in the same way.			
<ul> <li>Step 26: Yes add another subassembly.</li> <li>Step 27: Enter Case only as name for the subassembly.</li> <li>Step 28: Enter 1.</li> <li>Step 29: Choose Recycling only avoided demo7.</li> <li>Step 30: Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).</li> <li>Step 31: Click Next. Now SimaPro finally wants to know which materials are in the cases.</li> <li>Step 32: Yes, enter materials.</li> <li>Step 33: Select Plastics.</li> <li>Step 34: Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.</li> <li>Step 35: Enter the mass of the case, in this case 105 gram, or 0.105 kg.</li> <li>Step 36: The Subassembly is ready.</li> </ul>	Step 25:	No, This subassembly is ready.			
<ul> <li>Step 27: Enter Case only as name for the subassembly.</li> <li>Step 28: Enter 1.</li> <li>Step 29: Choose Recycling only avoided demo7.</li> <li>Step 30: Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).</li> <li>Step 31: Click Next. Now SimaPro finally wants to know which materials are in the cases.</li> <li>Step 32: Yes, enter materials.</li> <li>Step 33: Select Plastics.</li> <li>Step 34: Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.</li> <li>Step 35: Enter the mass of the case, in this case 105 gram, or 0.105 kg.</li> <li>Step 36: The Subassembly is ready.</li> </ul>	Step 26:	Yes add another subassembly.			
<ul> <li>Step 28: Enter 1.</li> <li>Step 29: Choose Recycling only avoided demo7.</li> <li>Step 30: Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).</li> <li>Step 31: Click Next. Now SimaPro finally wants to know which materials are in the cases.</li> <li>Step 32: Yes, enter materials.</li> <li>Step 33: Select Plastics.</li> <li>Step 34: Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.</li> <li>Step 35: Enter the mass of the case, in this case 105 gram, or 0.105 kg.</li> <li>Step 36: The Subassembly is ready.</li> </ul>	Step 27:	Enter Case only as name for the subassembly.			
<ul> <li>Step 29: Choose Recycling only avoided demo7.</li> <li>Step 30: Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).</li> <li>Step 31: Click Next. Now SimaPro finally wants to know which materials are in the cases.</li> <li>Step 32: Yes, enter materials.</li> <li>Step 33: Select Plastics.</li> <li>Step 34: Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.</li> <li>Step 35: Enter the mass of the case, in this case 105 gram, or 0.105 kg.</li> <li>Step 36: The Subassembly is ready.</li> </ul>	Step 28:	Enter 1.			
Step 30:Enter 100% in the held waste, indicating that all cases are sent to the waste scenario you just selected (recycling).Step 31:Click Next. Now SimaPro finally wants to know which materials are in the cases.Step 32:Yes, enter materials.Step 33:Select Plastics.Step 34:Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.Step 35:Enter the mass of the case, in this case 105 gram, or 0.105 kg.Step 36:The Subassembly is ready.Step 37:No. do not enter other subassembly (or you may want to experiment with a separate subassembly for	Step 29:	Choose Recycling only avoided demo7.			
Step 31:Click Next. Now SimaPro finally wants to know which materials are in the cases.Step 32:Yes, enter materials.Step 33:Select Plastics.Step 34:Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.Step 35:Enter the mass of the case, in this case 105 gram, or 0.105 kg.Step 36:The Subassembly is ready.Step 37:No. do not enter other subassembly (or you may want to experiment with a separate subassembly for	Step 30:	Enter 100% in the field waste, indicating that all cases are sent to the waste scenario you just selected (recycling).			
Step 32:Yes, enter materials.Step 33:Select Plastics.Step 34:Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.Step 35:Enter the mass of the case, in this case 105 gram, or 0.105 kg.Step 36:The Subassembly is ready.Step 37:No. do not enter other subassembly (or you may want to experiment with a separate subassembly for	Step 31:	Click Next. Now SimaPro finally wants to know which materials are in the cases.			
Step 33:Select Plastics.Step 34:Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.Step 35:Enter the mass of the case, in this case 105 gram, or 0.105 kg.Step 36:The Subassembly is ready.Step 37:No. do not enter other subassembly (or your may want to experiment with a separate subassembly for	Step 32:	Yes, enter materials.			
Step 34:Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.Step 35:Enter the mass of the case, in this case 105 gram, or 0.105 kg.Step 36:The Subassembly is ready.Step 37:No. do not enter other subassembly (or your may want to experiment with a separate subassembly for	Step 33:	Select Plastics.			
Step 35:       Enter the mass of the case, in this case 105 gram, or 0.105 kg.         Step 36:       The Subassembly is ready.         Step 37:       No. do not enter other subassembly (or your may want to experiment with a separate subassembly for	Step 34:	Select Polypropylene granulate at plant/RER S demo 7. This is the main material for the case.			
Step 36: The Subassembly is ready.	Step 35:	Enter the mass of the case, in this case 105 gram, or 0.105 kg.			
Step 37: No do not enter other subassembly (or you may want to experiment with a separate subassembly for	Step 36:	The Subassembly is ready.			
the printing color.	Step 37:	No, do not enter other subassembly (or you may want to experiment with a separate subassembly for the printing color.			

### SimaPro §

Step 38:	Yes, Add processes to the life cycle
Step 39:	Choose Transport
Step 40:	Choose Transport, van <3.5 t/RER S demo7
Step 41:	Enter 0.024 tkm or 24 kgkm. The weight of the CD-ROM is 121 gram. Multiply by the average
	transport distance (200 km). The (rounded) value is thus 0.024 tkm
Step 42:	No, do not enter additional processes (the processes needed for the recycling are already in the
	selected recycling scenario)
Step 43:	No, do not add additional life cycles
Step 44:	Click Next
After step 44,	Please confirm that you want to save the product system. Give the product system a name such as
	CD-ROM with recycling

### 8.3 Analyzing the results

#### 8.3.1 Analyzing the product system without recycling

Open the Product system without recycling. Here you see an overview of the data you have just entered.



Next, click the Network button is to get an overview of the process system, like below. You can see the Polyvinylchloride, Aluminium and Polypropylene flows in the assembly and the life cycle. The Municipal waste handling has a relatively low contribution. The waste scenario splits the waste stream in a part that is landfilled and a part that is incinerated. SimaPro has special waste treatment records to model the incineration and landfill. SimaPro automatically analyzes the material content in the waste flows and connects them to the proper waste treatment record (for this, each material has a label that describes the waste type).

In this example we used the avoided emission example, meaning that the electricity generated in the incineration process is assumed to avoid regular Dutch electricity production. You can see that this electricity has a negative environmental load. Use the Product system to change the waste scenario and regenerate the tree to inspect other waste scenarios. For instance use Household waste/NL S demo7.



Figure 48: CD-ROM without recycling

#### 8.3.2 Analyzing the product system with recycling

A similar analysis can be made of the system with recycling. After you click the process network button is please set the cut-off level at 0% for a complete overview, as shown below. You will now see that two subassemblies feed into the main assembly, and that the end-of-life treatment is different. A disposal scenario feeds into a disassembly, and from there, you have two separate disposal scenarios for the CD-ROM and the case. The impacts of the CD-ROM incineration are small, as the avoided electricity production avoids all impacts. The impacts of recycling the case are clearly negative, as recycling leads to a significant avoidance of the Polypropylene production. This leads to an overall negative impact for the whole disposal. Note that a transport process is connected to the life cycle. The impact of this collection effort is clearly lower compared to the benefits associated with the recycling system.

### SimaPro §



Figure 49: Inspection of tree CD-ROM with recycling

#### 8.3.3 Comparing both systems

Now select both product systems (click both systems, while holding the CTRL key down), and click Compare. Choose the impact assessment method you want to use. The recycling system is indeed preferred over the traditional disposal system if one uses the single score presentation.


Comparing 1 p 'Life Cycle\_CD-ROM without recycling' with 1 p 'Life Cycle\_CD-ROM with recycling'; Method: ReCIPe Endpoint (H) V1.08 / Europe ReCIPe H/A / Single score

Note that the outcome is heavily dependent on the way the benefits of recycling and energy reclamation from incineration are modeled.

### 8.3.4 Detailed analysis using the traditional user interface

Working with product systems is easy but it has some limitations. If you want to understand the details of the system you have built, go to the Product stages section. Under Assembly, subcategory Others, you will find the four assemblies you have defined in the Wizard. You can open these and inspect or edit them. You will also find the life cycles, disposal scenarios and disassembly stages under Others. Note that if you make changes in these Product stages, these changes will not be made in the Product systems.

Figure 50: Comparison CD-ROM with recycling with CD-ROM without recycling

## SimaPro 🗳

# 9 Lesson 4: Using Input Output Data

Overview	
What you will learn	How and when to use input output data
Required entry level	Lesson 1 should be completed
Recommended reading	'Introduction to LCA with SimaPro'. Chapter 8 provides some background; it is recommended, but not essential to read it.
Project needed	Tutorial with wood example, or any other project. Activate the library 'USA Input Output Database'. Please note that this library is not available in the demo version.
Approximate time needed	30-45 minutes

### 9.1 Introduction

SimaPro includes a comprehensive Input output database containing environmental data for all 500+ commodities in the USA economy. Commodities are generic names of groups of products and services, such as iron and steel, but also "Banking services". Data is specified per \$ trade value. This type of data opens up many new possibilities.

## 9.2 Problem 1: Priorities for sustainable consumption

The Japanese, Dutch and Danish governments as well as the Joint European Research Centre are currently determining which priorities should be set for policies aiming at reducing the environmental load of consumers.

### 9.2.1 The SimaPro solution

Determine the average spending by consumers on product groups, and link these to the Input output database. Such expenditure patterns are usually available at statistic bureaus, as they are needed to determine inflation figures.

To illustrate the idea, we will compare the environmental impacts of spending one dollar on a cinema or theatre with spending one dollar at a restaurant. Before starting, make sure that the library USA Input Output Database (under Libraries in Goal and Scope) is selected. Then go to Processes\Material\Input Output\USA 2002, and select Food services and drinking

places and Motion picture and video industries. Clicking the compare button **will** show that from a sustainable consumption point of view, it would be better if consumers would shift from spending money in restaurants to spending money in movie theatres.



9



Figure 51: Comparing Food services and drinking places with Motion picture and video industries

### 9.3 Problem 2: Guiding strategic investments

Determine the environmental impacts of changing the business portfolio for a company that is in the entertainment sector.

### 9.3.1 The SimaPro solution

Suppose your company is managing restaurant chains, and is contemplating to expand to other fields of entertainment, like movies and cinemas. In this case, the comparison described above can also be used to estimate the impact on the overall performance of the company. It provides a quick view of the probable changes of the eco-efficiency ratio. For instance, the annual  $CO_2$  emission per unit of turnover will be substantially reduced. Again, some care must be taken regarding exactness, but the general trend will be quite reliable.

### 9.4 Problem 3: Including the impact of services in the LCA

The main costs of producing a Demo booklet and Demo CD for SimaPro are in their design and distribution. In a traditional LCA these services are often not included.



#### 9.4.1 The SimaPro solution

Determine the costs spent per booklet and CD, and select the commodities that are representing these costs. The table below shows the basic data and the commodities they belong to.

ltem	Amount	Commodity
Development cost	\$2	Book publishers
Graphic design	\$2.10	Book publishers
Printing	\$2	Printing
CD production	\$1	Magnetic and optical recording media manufacturing
Postage	\$3.75	Postal service

Create a new assembly, adding the above data under Materials/Assemblies. Click Network 🔤 and set the cut-off at 9% to arrive at the following figure (if you get a calculation warning message click Continue).



Figure 52: Network of environmental load connected to printing booklet and CD

The network indicates that the environmental loads connected to printing the booklet are the most dominant. After that the postage has the most influence. In the example, we assumed that only regular mail was used. You can experiment changing postage from regular mail to courier service. In that case, since both are in the same sector, you just need to change the cost. Finally, the environmental load of the costs for developing the booklet (at the offices of PRé), as well as the graphic design companies are also quite important.

#### 9.4.2 Limitations

The example also shows some limitations. For instance, we cannot distinguish between different printing techniques, or different ways to send mail. Within a commodity, the only determining factor of the environmental load is the value. Another shortcoming is that it is difficult to determine the impacts of waste handling.

#### 9.4.3 Hybrid LCA

To compensate for these shortcomings, SimaPro supports the use of Hybrid LCA. This means you can use traditional LCA processes for printing and papermaking, and add a "normal" waste scenario, while you use the Input output data to model the services.

## SimaPro 🗳

# 10 Lesson 5: Solving the Weighting Debate

Overview				
What you will learn	How to use the weighting triangle. This is a powerful way to involve stakeholders in solving weighting problems when interpreting LCA results			
Required entry level	Lesson 1			
Recommended reading	'Introduction to LCA with SimaPro', chapter 4 is essential reading material			
Project needed	Tutorial with wood example, or any other project			
Approximate time needed	15-30 minutes			

### 10.1 The problem

Weighting across impact categories is not allowed for public comparisons (ISO 14042). So how do you compare the environmental load of two materials without using the default weighting sets? We take the case of comparing the production of two types of thermoplastics: 1 kg LDPE and 1 kg of HDPE.

### 10.2 The SimaPro solution

Under Libraries select the Industry data 2.0 library. Note that some demo versions may not have this database. Go to Processes/Materials/Plastics/Thermoplasts, select LDPE resin E and HDPE resin E. Click the Compare button select the ReCiPe Endpoint H/A method, and go to Single score. You will see that the HDPE seems to have a slightly lower environmental load per kilo. However, the Single score is calculated using a weighting set, and this is not what we want. Go to Normalization, and make sure you have not selected the checkbox "Per impact category".

10



Figure 53: Comparing two products without using default weighing sets

Under this view, it is evident that HDPE has a lower score on Human Health, but a higher score on Resources. This is because more energy from fossil fuels is used in the production process.

Now click the triangle button to get the window shown below. On the sides of the triangle, the weights for each of the three damage categories are plotted between 0 and 100%. All points within the triangle can be seen as a possible weighting set. In the figure below, we added white lines to indicate the weighting set used as default for the ReCiPe method (these will not show on your screen):

- Human Health 40%
- Ecosystems 40%
- Resources 20%

One can imagine that there are weighting sets for which both plastics will have the same environmental loads. These points form the "line of indifference". In this example, all the points on the left-hand side of this line are weighting sets for which HDPE has a lower environmental load (in blue). The red area indicates the weighting sets for which HDPE has a higher load. Whether HDPE is preferable or not clearly depends on the weighting set you apply.

## SimaPro 🗳



Figure 54: Triangle with weights of damage categories

The triangle does not solve the weighting problem, but you can now discuss the weighting issue in a much more constructive way. You can present the triangle to stakeholders and ask whether they would find it more reasonable if their weighting set would be in the blue or the red area, or somewhere close to the line of indifference. Or to put it in another way, would it be conceivable that the weight for human health is much lower than 40%, while the weight for resources is much higher than 40%? Experience shows that these types of discussions with stakeholders can be productive.

# 11 Lesson 6: Monte Carlo Analysis

Overview	
What you will learn	Use and interpret Monte Carlo simulations in SimaPro to determine the absolute uncertainty, and to determine how certain you can be if the difference between two product systems is indeed real.
Required entry level	Lesson 1 and 3 must be completed first. Lesson 6 elaborates on the example of the coffee machine used in lesson 1. Lesson 3 provides a better understanding of the disposal scenarios used here.
Recommended reading	'Introduction to LCA with SimaPro'. Chapter 9 is essential.
Project needed	Introduction to SimaPro
Approximate time needed	45-60 minutes

## 11.1 The problem

LCA data is full of uncertain numbers. These uncertainties can have different causes, like uncertain measurements, or uncertainty about how representative a figure is of the actual problem we are studying. This means we must ask ourselves how certain or uncertain our results are, especially when we are comparing data.

In this example, we will use the coffee machine example. We focus on whether or not it is useful to recycle the aluminum coffee machines (model Pro).

## 11.2 The SimaPro solution

Uncertainty calculations can only be made in SimaPro Analyst, SimaPro Developer, and SimaPro PhD. You can specify the uncertainty on each input and output of a process, or a product stage. Almost all uncertainty values of flows in the ecoinvent database are specified as log normal distribution. Please note that with the limited demo version, you may not be able to actually carry out this example.

SimaPro supports 4 types of distributions, explained below:

Distribution	Data needed	Graphical presentation
Range	Min and max value	
Triangular	Min and max value	
Normal distribution	Standard deviation	
Log normal distribution	Standard deviation	

11



### 11.3 Recycling of model Pro

The recycling model is described in a Disposal scenario, see also lesson 3. To inspect this, select the Disposal scenario for model Pro. This can be found under Product stages/Disposal/Coffee machine (demo)/Disposal scenario for model Pro.



Generate a Network to get a window like the one shown below (node cut-off set at 1.7%).



The main uncertainties in the system are summarized below:

- Transport for collection; uncertainty is at least a factor 2
- Energy consumption for disassembly; uncertainty is a factor 1.5

This data has been specified in the Disposal and Disassembly scenarios as a lognormal distribution with a square root of the distribution interval of 2. This means 95% of all values are between the estimated value divided by two and the estimated value times two.

		Enter the tr	uncertaint ansport dis	y data for stance	
S Edit disposal scenario 'Disposal scenario for model Pro'					
Input/output Parameters					
Name Image					
Disposal scenario for model Pro					в
Referring to accombly	Amount	Unit			
Assembly model Pro (aluminium)	1	p			
_				1	
Processes	Amount	Unit	Distribution	SD^2 or 2*S	DMin
Transport, lorry 28t/CH S demo7	1,2	tkm	Lognormal	2	
Transport, van <3.5t/RER S demo7	1,6	tkm	Lognormal	2	I, I
•					•

Figure 56: Entering uncertainties



### 11.4 Does the recycling system seem to be beneficial?

In order to understand the usefulness of the recycling system, we will now compare two life cycles: one with, and the other without, recycling. We have seen in example 1 that the life cycle is heavily dominated by the energy consumption, and the use of filters. As these parameters are the same for both systems, we will use two special versions of the life cycle, see below.



Select both life cycles, and click Compare. If we compare per impact category, the picture is mixed. For instance, climate change will be reduced with recycling, but urban land occupation will be increased.

You will see that on the Single score level, there is indeed a difference. The recycling system seems to have its benefits.

### 11.5 Monte Carlo analysis

To address the uncertainties, minimize the comparison window, select both life cycles, and click the Monte Carlo button . SimaPro will now start the uncertainty analysis. It does so by repeating the comparison. Each time another value is selected for the transport and energy, as these were the factors specified with an uncertainty range. The different samples are chosen in such a way that all samples together conform to the distribution specified in the data.



Figure 57: Calculating uncertainty analysis

Figure 57 shows the distribution of the difference between the weighted single score for each run. An important feature of SimaPro is that for each comparison the same samples are used. In other words, the correlations are taken into account. To date, SimaPro is the only software package that can do this. You may stop the calculation after a couple of hundred runs.

### 11.6 Comparing uncertainty per impact category

After you stop the calculation, a comparison is shown on the impact category level. Each bar represents an impact category.



#### Figure 58: Uncertainty analysis

The red bars represent the number of times the scenario without recycling had a lower load than the life cycle with recycling. For instance, it shows that in 100% of the cases the Metal depletion score is lower without recycling. In about 2% of the cases the Climate Change Human Health score is lower, meaning that it is almost certain that for climate change recycling would be better. For some other impact categories it is not so clear if recycling is better.

Please take some time to explore the many other features of this window, and check the comparisons per emission in the inventory section.

### 11.7 Absolute uncertainty

You may also want to run the Monte Carlo analysis for the take-back system not for comparison purposes, but to see the absolute uncertainty. Select this life cycle and click the Monte Carlo button. Please note that this can only be done when uncertainty data is included.

## SimaPro \delta





In this graph, the 95% confidence interval is given for each impact category, and as you can see the range is considerable. Technically it would be no problem to show such a range in a comparison, but this would only create confusion, as the absolute uncertainty of a single system is usually much higher than the differential uncertainty, due to the correlations.

It is also possible to inspect the uncertainty of an individual emission, or for an impact category. Figure 60 shows the uncertainty graph for climate change.





### 11.8 Final remark on this example

The example shown here is somewhat artificial, as only a few flows have an uncertainty range. If you use the ecoinvent database, most flows have uncertainty data. This will provide real insight in the uncertainty analysis.

### 11.9 Uncertainty of parameters

Parameters can also contain uncertainty information, and this information is evaluated in the same way as in the Monte Carlo analysis. There are many applications for this feature, but here we show how you can add an uncertainty factor to an allocation parameter.

In the figure below we show how you can define a parameter for the uncertainty on the allocation of Chlorine production, if you use economic allocation. Note that the sum of the allocation factor for Chlorine and Sodium will always add up to 100%, even while in a Monte Carlo procedure.

Define pa allocation mode	arameters for n and transport	Define expressions, in this case for the sodium allocation factor. The formula in this example is very simple, but you can define all kinds of expressions.	Define uncertainty range for the allocation percentage; you can also apply normal, lognormal and triangular distributions	Parameters that are only relevant within a process can be hidden, so they do not appear in parameter lists elsewhere
	Documentation   Input/outp Input parameters Name d_econ_all barge (Insert line here) Calculated parameters	ut Parameters System description Value Distribution SD 2 or 2*SD 60 Uniform 1 Undefined	Min Max Hide Comment 45 65 allocation % for chlo set barge=1 if a ship	rine based on market price is used
	Name na_econ_all (Insert line here)	Expression 100-d_econ_all	Comment allocation % for sodium. This definit percentages add up to 100%, even	ion ensures that the total during Monte Carlo runs.



Below we show how you can apply these parameters.



This example gives only one of many applications of uncertainty functionality on parameters.

# 12 Further Developing your Skills

When you have completed most of the lessons in this tutorial, you should be able to carry out detailed LCA studies with SimaPro. You will experience that making LCAs is a skill you will continue develop with each study. as each LCA has its own specific issues. Make sure to carefully select and document your approach as you go along.

We would like to end this tutorial with the following suggestions for further learning:

- **Meet other practitioners.** If you want to meet other LCA practitioners, exchange views, and learn from others, we suggest you go to conferences. At www.pre-sustainability.com/events you can find an overview of the most important conferences, and where you can meet representatives of PRé or its international partner network. Particularly interesting are the SETAC conferences. During these conferences you can meet many experts and join all kinds of international working groups, such as those organized by the UNEP Life cycle Initiative.
- More training. If you want additional training, you can also look at http://www.pre-sustainability.com/training-calendarpre-consultants to find out where trainings are provided by PRé or the international partner network.
- **More reading.** There are a number of books on LCA. Unfortunately many seem to be rather theoretical (that is why we developed our own Introduction to LCA with SimaPro) but we can recommend the book of Bauman and Tillman, "The Hitchhiker's Guide to LCA".
- **Magazines.** There are several scientific magazines that cover LCA, but the most important are: o The journal of Cleaner Production (www.journals.elsevier.com/journal-of-cleaner-production/) o The international Journal of LCA (www.springer.com/environment/journal/11367)
- Internet. There are of course endless possibilities to learn, but we would like to mention:
  - o The LCA discussion list provides access to nearly 2500 LCA experts. See http://www.pre-sustainability.com/lcadiscussion-list
  - o www.lcacenter.org

If you need any help with SimaPro, contact our helpdesk, consultants or international partner network via www.pre-sustainability.com.

We wish you success and hope that through your activities, you can support decisions that will lead to more sustainable products and services at your organization.